

# RAYSYNC サーバー 管理マニュアル

Shenzhen Yunyu Technology Company Limited



#### ドキュメント情報

プロジェクト	Raysync 転送					
作者	Guocheng He	バージョン	V1.5			
タイトル	サーバー管理マニュアル	発売日	2020/10/15			
Pass by	組織	承認	製品部			

#### バージョン履歴

バージョ ン	変更説明	作者	変更日
1.0	ソフトウェアに従って、ユーザーマニュアルの初 版を完成させてください	Xinlei Wang	2019/4/28
1.1	ユーザーグループの設定を増やします	Xinlei Wang	2019/5/26
1.2	Alibaba クラウド OSS オブジェクトストレージ設 定を追加します	Xinlei Wang	2019/7/26
1.3	インストール作業が最適化された後、インストー ル操作、容量統計、Amazon S3 ストレージの設定 を更新します。	Ruyun Lou	2020/4/29
1.4	転送プロトコル設定の更新、メール通知、メール 認証、外部 Http(s)認証の追加、LDAP ドメインの ユーザーアカウントへのアカウント情報のイン ポート、そしてユーザーのパス設定の禁止しま す。	Guocheng He	2020/8/3
1.5	ポイントツーポイント転送の追加、ポイントツー ポイントログ、IP ホワイトリスト、通知の送信、 Auth A/C の設定	Guocheng He	2020/10/15



# 内容

1	は	t l	じめに	۲5
2	サ	L _	ーバー	- 管理マニュアル5
	2.	1	Win	idows サーバーの導入5
		2	2.1.1	インストール用の zip ファイルの取得5
		2	2.1.2	9 解凍5
		2	2.1.3	を起動する
		2	2.1.4	- サービス停止7
		2	2. 1. 5	- Raysync サービスの稼働状況を見る7
		2	2.1.6	・ポートマッピング
	2.	2	2 Lin	ux サーバーの導入
		2	2.2.1	ソフトウェアパッケージを入手8
		2	2.2.2	8 解凍
		2	2. 2. 3	インストールの初期化10
		2	) 2 4	- お動する 10
		2	2.2.1	10 ・ サービス停止 10
		2	2. 2. 0	10
		 2	 	Powerpo サービスの窃働状況を目ろ 10
		2	2.2.0	$ \text{Raysync} $ $ = C \wedge v / 称 剛 朳 孔 を 元 る$
	0	2		
	2.	. 3	3 官型	
		2	2.3.1	· 管理者コンソールにロクイン
		2	2.3.2	、サーバーの状態表示13
				2.3.2.1 ディスク容量       13         2.3.2.1 転行       13         132.3.2.1 転信       13
				2.3.2.3 ライセンス情報
				2.3.2.4 モニタリング情報14
				2.3.2.5 オンラインユーザー数15
		2	2.3.3	・サーバーの再起動15
		2	2.3.4	サーバーの停止16
		2	2.3.5	・サーバーの起動16
		2	2.3.6	)管理者コンソールのログアウト17
	2.	4	トサー	- バー有効化17
		2	2.4.1	オンライン有効化17
		V	Vebsit	te: www.raysync.io 🐁 Tel: +86 18681593969 🖾 Email:support@raysync.io

# 🗲 Raysync

2.4.2 オフライン有効化(windows)19
2.5 サーバー情報の編集22
2.5.1 サーバーアドレス23
2.5.2 UDP 加速ポート
2.5.3 UDP メッセージサイズ24
2.5.4 圧縮を有効化
2.6 転送情報 25
2.0 料区時報 20
2.6.3 ホイントツーホイント転送
2.6.4 ポイントツーポイントログ28
2.7 リンク管理
2.7.1 アップロード招待
2.7.1.1 リンクの詳細を見る
2.7.1.2 リンクをコピー
2.7.1.3 リンクをキャンセル
2.7.1.4 リンクを削除
2.7.1.5 検索
2.7.2 ダウンロードの共有32
2.7.2.1 リンクの詳細を見る
2.7.2.2 リンクをコピー
2.7.2.3 リンクを無効にする
2.7.2.4 リンクを削除
2.7.2.5 検索
2.7.3 メールアドレスの設定
2.8 ユーザー管理
2.8.1 ユーザー一覧
2.8.1.1 ユーザーの追加34
2.8.1.2 ユーザーの編集
2.8.1.3 ユーザーのロック
2.8.1.4 ユーザーのロックを解除する
2.8.1.5 検索
2.8.1.6 LDAL/AD ドメインアカウントのインポート
2.8.1.7 ユーザーアカウントの削除
2.8.1.8 ユーザーのオンライン状態の確認40
2.8.1.9 コンフィグ通知メール
2.8.2 ユーザーの容量占有率統計42
Website: www.raysync.io % Tel: +86 18681593969 Email:support@raysync.io

# 🗲 Raysync

	2.8.3 ユーザー操作記録	43
	2.8.4 ユーザーグループ	43
	2.8.4.1 ユーザーグループの作成	. 43
	2.8.4.2 ユーザーグループの編集	.44
	2.8.4.3 ユーザーグループのユーザーを表示する	45
	2.8.4.4 ユーザーグループにユーザーを追加する	46
	2.8.4.5 ユーザーグループのユーザーを削除する	47
	2.8.4.6 ユーザーグループの削除	. 47
	2.8.4.7 検索	. 48
	2.8.4.8 ユーサークルーノ谷重の百有半統計	48
	2.8.0	40
	2.8.5.1 LDAP/AD 設定	. 48
	2.8.5.2 メール認証	. 50
	2.8.5.3 Unix システム認証 2.8.5.4 対対 h++n 認証	.51
	2.0.0.4 7 http 認証	· 53
	2.8.7 Auth A/C 設定	55
	2.8.8 通知を送信	
	2.8.8.1 通知の追加	. 56
	2.0.0.2 (映光) 四和 2.8.8 3 通知の削除	. 50 59
	2.8.8.4 通知の受信するアカウントを表示	. 59
2	- 9 ストレージ設定	60
	2.9.1 ローカルストレージ	60
	2.9.2 Alibaba クラウド OSS	61
	2.9.3 Amazon S3	61
	2.9.4 S3 インターフェース対応ストレージ	62
	2.9.5 Azure Blob	62
2	.10 詳細設定	63
	2.10.1.1 TLS 証明書	63
	2.10.1.2 TLS 証明書	63
	2.10.1.3 TLS 証明書情報の表示	64
	2.10.1.4 TLS 証明書の再アップロード	64
	2.10.2 クライアント TLS	65
	2.10.3 MySQL 設定	67
	2.10.4 転送プロトコル	67
۲	Website: www.raysync.io 💊 Tel: +86 18681593969 🖂 Email:support@raysync.i	io



2.10.5 イベント通知69
2.10.6 その他の設定71
2.10.6.1 速度制限
2.10.6.2 ログファイルの保存場所71
2.10.6.3 ログファイル保存期間71
2.10.6.4 ファイルを閉じる72
2.10.6.5 ファイルの同期72
2.10.6.6 アカウントのロック74
2.10.6.7 弱いパスワード設定74
2.10.6.8 システム転送ホワイトリスト74
2.10.6.9 複数の IP アドレスに対応75
2.10.6.10 許可されたプロセス数75
2.10.6.11 ユーザーによるパスワードの変更を許可する
2.11 管理者情報を変更する76
2.12 個性的設定
2.12.1 アイコン、ロゴ、背景画像など77
2.12.2 ウェブページのキーワードをカスタマイズ
3. よくある質問



# 1 はじめに

深セン市雲語科技有限公司(以下、雲語科技)は、2010年に中国深センに本社と北京、上海、 成都に支社をそれぞれ設立しており、現在ビジネスは全世界をカバーしています。雲語科技は、 ビッグデータ転送の高速化とネットワーク最適化サービスに焦点を当てており、ビッグデータ時 代のデータ同期や情報のインタラクティブをより効率的にするために、様々な組織をサポートし ています。

#### 技術的なアドバンテージ

Raysync 転送エンジンは、データ転送業界をリードするの技術で顧客の越境転送、長距離転送、 大容量ファイル転送などの問題点を完璧に解決します。また、帯域幅効率を最大限にし、作業効 率を向上させることで、顧客から満足度の高いコメントを得ています。

#### サービスチーム:

Raysync 転送エンジンと従来のネットワークリソースを組み合わせる他、業界において経験豊富 な技術とサービスチームを擁しており、お客様に高速、安定、安全なネットワークサービスを提 供しています。企業のネットワークへの投資を大幅に節約し、効率性を向上させ、ネットワーク の利用をより手軽にしています。

# 2 サーバー管理マニュアル

### 2.1 Windows サーバーの導入

RaySync windows サーバーは、windows server 2008、windows server 2012、windows server 2016、 windows 7、windows 8、windows 10 プラットフォームの導入をサポートしています。

# 2.1.1 インストール用の zip ファイルの取得

<u>https://www.raysync.io/pricing/</u>にアクセスして、最新の zip ファイルをダウンロードしてく ださい。

プロ版または企業版をご購入された場合は、販売員から関連するインストールパッケージを入手 してください。

### 2.1.2 解凍

インストールディレクトリ(D:¥Program Files¥Raysync)に解凍すると、次のファイルが表示されます:



$\leftrightarrow \rightarrow \uparrow \uparrow \downarrow $	RaySync-5.0.0.8-7063-free-win32 > Raysync			
> 🖈 Quick access	Name	Date modified	Туре	Size
🗸 🗖 This PC	🔒 config	3/2/2020 3:50 PM	File folder	
E Dealaters	dist	3/2/2020 3:50 PM	File folder	
> Desktop	httpscert	3/2/2020 3:50 PM	File folder	
> 📋 Documents	proxy	3/2/2020 3:51 PM	File folder	
> 🕹 Downloads	tools	3/2/2020 3:50 PM	File folder	
> 👌 Music	AdminUnlockTool	3/2/2020 3:50 PM	Application	9,628 KE
> E Pictures	api-ms-win-core-console-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
Videos	📓 api-ms-win-core-datetime-l1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KE
	📓 api-ms-win-core-debug-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12. KB
> 🌇 Local Disk (C:)	api-ms-win-core-errorhandling-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
> 👝 work (E:)	api-ms-win-core-file-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	15 KB
🕨 🔿 Network	api-ms-win-core-file-I1-2-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	🚳 api-ms-win-core-file-I2-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
🕨 🔩 Homegroup	📓 api-ms-win-core-handle-l1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	api-ms-win-core-heap-l1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	api-ms-win-core-interlocked-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	🗟 api-ms-win-core-libraryloader-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12. KB
	api-ms-win-core-localization-I1-2-0.dll	3/2/2020 3:50 PM	Application extens	14 KB
	🗟 api-ms-win-core-memory-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	api-ms-win-core-namedpipe-I1-1-0.dll	3/2/2020 3:50 PM	Application extens	12 KB
	api-ms-win-core-processenvironment-l1	3/2/2020 3:50 PM	Application extens	13 KB

#### ファイルリストの説明:

ファイル名	説明
設定	Raysync 転送サービス設定のファイル
分配	RaySync ウェブサービス
httpscert	Https 証明書
ログ	Raysync 転送サービスのログファイル (起動後に作成)
プロキシ	Raysync 転送加速サービス
ツール	オフライン有効化コードのツール
ライセンス	有効化コード
ユーザー	Raysync ユーザーストレージ
raysync-webmon.exe	デーモン処理
AdminUnlockTool.exe	Raysync バックグラウンド管理者パスワードロック解除サービス
raysync-web.exe	ファイル転送サービス
rayfile-s.exe	レイファイル転送サービス
start.bat	RaySync 転送サービスの開始
stop.bat	RaySync 転送サービスの停止
status.bat	Raysync サービスの稼働状況を見る
AdminInitPwd	管理者デフォルトの初期パスワードファイル(サーバー起動後に生成)
serviceStart.exe	自動開始サービス
serviceDel.exe	自動開始サービスをオフにする
Website: www.rays	ync.io 🗞 Tel: +86 18681593969 🖂 Email:support@raysync.io



ファイル名	説明
raysync-update.exe	Raysync アップデートサービス
version.txt	バージョン確認

# 2.1.3 起動する

start.bat をダブルクリックして Raysync 転送サービスを開始します。起動が成功してから、 任意のキーを押してウィンドウを閉じます。



# 2.1.4 サービス停止

stop.bat をダブルクリックして Raysync 転送サービスを停止します。停止が成功してから、任意のキーを押してウィンドウを閉じます。



# 2.1.5 Raysync サービスの稼働状況を見る

Status.bat をダブルクリックすると、Raysync 転送サービスの稼働状況が表示されます。確認 したら、任意のキーを押してウィンドウを閉じます。



C:\Windows\system32\cmd.exe	<u> </u>	>
raysync-webmon is already running raysync-web is already running rayfile-s is already running raysync-update is already running		

# 2.1.6 ポートマッピング

サーバー上では、NAT ゲートウェイに展開され、かつイントラネット IP しかない場合は、ルー ターの NAT に以下の 5 つのポートをマッピングする必要があります:

TCP:8090

TCP:9090

TCP:2442

TCP:2443

UDP:32001

# 2.2 Linux サーバーの導入

Raysync linux サーバーの導入は、ubuntu14.0.x、centos6.5以上のバージョンに対応しています。

# 2.2.1 ソフトウェアパッケージを入手

https://www.raysync.io/pricing/にアクセスして、最新の zip ファイルをダウンロードしてください。

プロ版または企業版をご購入された場合は、販売員から関連するインストールパッケージを入手 してください。

#### 2.2.2 解凍

インストールディレクトリーに解凍します。例えば/opt/Raysync のようなインストールディレクトリに解凍し、その下のディレクトリで-zxvf xxxx.tar.gz を実行してインストールパッケージを開きます:

[root@iZwz9ivic58czwgtdc75bsZ Raysync]# tar -zxvf RaySync\_FTP-3.0.7.3-4987\_Free-linux\_64.tar.gz

以下のファイルが表示されます:



[root@local]	hos	st Rav	/Svnc	l# 11				
total 90016								
-rwxr-xr	1	root	root	20364357	Mar	2	15:50	AdminUnlockTool.bin
drwxr-xr	2	root	root	40	Mar	2	15:50	config
drwxr-xr	4	root	root	30	Mar	2	15:50	dist
-rwxr-xr	1	root	root	17	Mar	2	15:50	encryption.json
drwxr-xr	2	root	root	69	Mar	2	15:50	httpscert
-rwxr-xr	1	root	root	9235	Mar	2	15:50	install.sh
-rwxr-xr	1	root	root	3649897	Mar	2	15:50	ip.ipdb
-rwxr-xr	1	root	root	22	Apr	8	17:36	license.txt
drwxr-xr	3	root	root	59	Mar	2	15:50	proxy
-rwxr-xr	1	root	root	29284072	Mar	2	15:50	rayfile-s
-rwxr-xr	1	root	root	56	Mar	2	15:50	raysyncA
-rwxr-xr	1	root	root	207	Mar	2	15:50	RaySyncServer.sh
-rwxr-xr	1	root	root	5112560	Mar	2	15:50	raysync-update
-rwxr-xr	1	root	root	26165695	Mar	2	15:50	raysync-web.bin
-rwxr-xr	1	root	root	7528216	Mar	2	15:50	raysync-webmon
-rwxr-xr	1	root	root	677	Mar	2	15:50	start.sh
-rwxr-xr	1	root	root	1625	Mar	2	15:50	status.sh
-rwxr-xr	1	root	root	3370	Mar	2	15:50	stop.sh
drwxr-xr	4	root	root	51	Mar	2	15:50	tools
-rwxr-xr	1	root	root	3306	Mar	2	15:50	uninstall.sh
-rwxr-xr	1	root	root	519	Mar	2	15:50	update.ini
-rwxr-xr	1	root	root	2809	Mar	2	15:50	upgrade.sh
-rwxr-xr	1	root	root	7	Mar	2	15:50	version.txt

#### ファイルリストの説明:

ファイル名	説明
設定	Raysync 転送サービス設定のファイル
分配	RaySync ウェブサービス
httpscert	Https 証明書
ログ	Raysync 転送サービスのログファイル (起動後に作成)
プロキシ	Raysync 転送加速サービス
ライセンス	有効化コード
ユーザー	Raysync ユーザーストレージ
raysync-webmon.exe	デーモン処理
AdminUnlockTool.exe	Raysync バックグラウンド管理者パスワードロック解除サービス
raysync-web.exe	ファイル転送サービス
rayfile-s.exe	レイファイル転送サービス
start.sh	RaySync 転送サービスの開始
stop.sh	RaySync 転送サービスの停止
status.sh	Raysync サービスの稼働状況を見る
インストール	スクリプトをインストールし、起動後に自動的に立ち上がるように設定しま す
アンインストール	起動後に自動的に起動をキャンセルします
Website: www.rays	ync.io 🐁 Tel: +86 18681593969 🖂 Email:support@raysync.io



ファイル名	説明
encryption.json	パスワード暗号化を使用して設定を保存します
version.txt	バージョン確認
ツール	オフライン有効化コードのツール
AdminInitPwd	管理者デフォルトの初期パスワードファイル(サーバー起動後に生成)
raysync-update.exe	Raysync アップデートサービス

# 2.2.3 インストールの初期化

#### #./install

インストールが通常通りに完了したことは、インストールの初期化が完了し、起動後に自動的に 立ち上がるよう、設定が成功したことを意味します。

```
root@iZwz9bx129zrquxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8# ./install.sh
Successfully installed.
root@iZwz9bx129zrquxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8#
```

# 2.2.4 起動する

./start.shを実行して、RaySync 転送サービスを開始します

```
[root@localhost RaySync]# ./start.sh
raysync-webmon.sh is running...
raysync-web is running...
raysync-mon is running...
rayfile-s is running...
raysync-update is running...
[root@localhost RaySync]#
```

# 2.2.5 サービス停止

./stop. sh を実行して、RaySync 転送サービスを停止します

```
[root@localhost RaySync]# ./stop.sh
Stop raysync-webmon successed
Stop RaySync successed
```

# 2.2.6 Raysync サービスの稼働状況を見る

Status. bat をダブルクリックして、Raysync サービスの稼働状況を表示します:

```
[root@localhost RaySync]# ./status.sh
raysync-webmon.sh is running...
raysync-web is running...
raysync-mon is running...
rayfile-s is running...
raysync-update is running...
```



# 2.2.7 ポートマッピング

サーバー上では、NAT ゲートウェイに展開され、かつイントラネット IP しかない場合は、ルー ターの NAT に以下の 5 つのポートをマッピングする必要があります:

サービス説明	プロトカルタイプ	ポート
ユーザー http サービスポート ユーザー https サービスポート	TCP	8090 8091
管理者 http サービスポート 管理者 https サービス・ポート	TCP	9090 9091
暗号化されていないサービスポート TLS 暗号 化された転送ポート	TCP	2442 2443
UDP 加速転送サービスポート	UDP	32001

## 2.3 管理者操作マニュアル

サーバーが実行されたら、Google Chrome で xx. xx. xx を開きます: IP:9090/admin 例: 172.16.5.77:9090/admin/

# 2.3.1 管理者コンソールにログイン

初期管理者アカウント: admin

管理者の初期パスワード:

Windows の場合は、AdminInitPwd ファイルを開き、tar.gz ファイル内のパスワードをコピーしてください。

Name	×	Date modified	Туре	Size
config		4/27/2020 11:44 AM	File folder	
dist		4/21/2020 3:14 PM	File folder	
httpscert		4/21/2020 3:14 PM	File folder	
log		4/27/2020 11:36 AM	File folder	
proxy		4/27/2020 11:36 AM	File folder	
tools		4/21/2020 3:14 PM	File folder	
AdminInitPwd		4/27/2020 11:36 AM	File	1 KB
AdminUnlockTool		4/21/2020 3:13 PM	Application	9,628 KB
api-ms-win-core-console-I1-1-0.dll		4/21/2020 3:13 PM	Application extens	12 KB

Linux の場合、AdminInitPwd を cat してパスワードを表示します。

% Tel: +86 18681593969



root@iZwz9bx129zrquxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8# cat Adm	ninInitPwd
3u(_w%⊧c	
root@iZwz9bx129zrquxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8# 🚦	

デフォルトのサーバーアカウント/パスワードを入力してログインします。

😴 Raysynd	
Admin Management Login	
Account	
Password	
Log In	

初回ログイン時に、パスワードを変更してください。

新しいパスワードは、スペースを使用できません。大文字、小文字、数字、3つの組み合わせを 8~20文字以内に設定する必要があります。パスワードとアカウントは同じにできません。



[OK]をクリックしてパスワードをリセットし、新しいパスワードでログインします。



# 2.3.2 サーバーの状態表示

このインターフェースではサーバー設定情報、Raysync ソフトウェアの状態、オンラインユーザー数、ライセンスの有効化状態、CPUと関連するネットワークカードの監視情報が表示されます。

# 2.3.2.1 ディスク容量



### 2.3.2.2 動作状態

😂 Raysync Enterpr	<i>iSe</i> Admin Console				=	admin 🗸
⊑ ⊟ Server	Server					
t≣ Transfer ^	User Connection	s	Storage Status	Select Disk: 📝 👻	License Information:	
Transfering	Online Users	Client Connections	Free79.02%		Activated (10240Mbps)	tails
Transfer log	0	0				
Point to point tran	0	0			Commentation .	
Point to point log	After users connect counted as one clie	ting with Raysync Client, each connected webpage is ent connection.		Used20.97%	Server Status	
🔗 Share Manager 🛛 🥎			39.49 G	B free of 49.98 GB	Kunning	
Invitation upload						
Share download	Main Informa	tion Modify	CPU Info			
Email	Server Name:	Raysync server	30	🔵 Ci	PU Usage (%)	
🛋 Users Manager \land	Version:	5.0.5.8	25			
Users	MAC Address:	00:50:56:8a:27:e8	20			6
Operation records	OS:	Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	15			
User group	Host 🕄		10			
Third-party auth	UDP Port:	32001	5			
Auth A/C setting	UDP Package Siz	e: 1200	0			
Space statistics	Compression <b>O</b> :	Enabled	¢.			0
Send notification	Bandwidth:	0				
Storage config	License:		NIC Info		Select Network Card: doc	ker0 🗸
Advanced Setting ~				197		

Website: www.raysync.io

& Tel: +86 18681593969



# 2.3.2.3 ライセンス情報

😂 Raysync Enterp	<i>rise</i>   Admin Console	8			admin ~
Ξ	Server				
Server					
t≣ Transfer ^	User Connection	S	Storage Status	Select Disk: 📝 💌	License Information:
Transfering	Online Users	Client Connections	Free79.02%		Activated (10240Mbps)     Details
Transfer log	0	0			
Point to point tran		0			Cerver Status
Point to point log	After users connect counted as one clie	ting with Raysync Client, each connected webpage is ent connection.	<ul> <li>F</li> </ul>	vee Used	Running
🔗 Share Manager \land			39.49 GB	I free of 49.98 GB	
Invitation upload	-				
Share download	Main Informa	tion Modify	CPU Info		
Email	Server Name:	Raysync server	30	CF	PU Usage (%)
🞫 Users Manager 🛛 🗠	Version:	5.0.5.8	25 0	- Ann	
Users	MAC Address:	00:50:56:8a:27:e8	20		
Operation records	OS:	Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	15		
User group	Host 🕒:		10		
Third-party auth	UDP Port:	32001	5		
Auth A/C setting	UDP Package Siz	ter 1200	0		
Space statistics	Compression 🖲:	Enabled	<sup>o</sup>		0
Send notification	Bandwidth:	0			
Storage config	License:		NIC Info		Select Network Card: docker0 🗸
Advanced Setting ~					

# 2.3.2.4 モニタリング情報





ネットワークカード情報:

& Tel: +86 18681593969



Server Name:	Raysync server		CPU Usage (%)
Version:	5.0.5.8	30	
MAC Address:	00:50:56:8a:27:e8	25 ~~~	and a Manual and a series of the
OS:	Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	20	
Host Ot		40	
UDP Port:	32001	10	
UDP Package S	ize: 1200	5	
Compression @	Enabled	0 @	
Bandwidth:	0		
Bandwidth:	0	NIC Info	Salari Natarah Par
n Bandwidth: License:	0	NIC Info	Select Network Can
Bandwidth: License:	0	NIC Info	Select Network Can <ul> <li>Incoming Speed (Mbps)</li> <li>Outgoing Speed (Mbps)</li> </ul>
Bandwidth: License:	0 Shutdown server C, Reboot server	NIC Info	Select Network Carc incoming Speed (Mtps) 🕘 Outgoing Speed (Mtps)
Bandwidth: License:	0 Shutdown server	NIC Info	Select Network Carc  Incoming Speed (Mtps) 🔴 Outgoing Speed (Mtps)
Bandwidth: License:	0 Shuddown server C, Roboot server	NIC Info	Select Network Carc incoming Speed (Mitps) 🔮 Outgoing Speed (Mitps)
Bandwidth: License:	0 Shutdown server	NIC Info 1.0 0.9 0.8 0.7 0.6	Select Network Card 🌒 Incoming Speed (Mtps) 🔴 Outgoing Speed (Mtps)
Bandwidth: License: O	0 Shutdown server	NIC Info 1.0 0.9 0.8 0.7 0.6 0.5	Select Network Carc
Bandwidth: License: O	0 Shutdown server C, Rebuck server	NIC Info 1.0 0.9 0.8 0.7 0.6 0.5 0.4	Select Network Card
Bandwidth: License:	0 Shuddown server	NIC Info 10 09 08 07 06 05 04 03	Select Network Card 🌒 Incoming Speed (Mtps) 🥚 Outgoing Speed (Mtps)
Bandwidth: Lienne:	0 Shutdown server C, Robuct server	NIC Info 10 09 08 07 06 05 04 03 02	Select Network Card
Bandwidth: License	0 Shuhdown server	NIC Info 10 0.9 0.8 0.7 0.6 0.5 0.4 0.3 0.2 0.1	Select Network Can

2.3.2.5 オンラインユーザー数



# 2.3.3 サーバーの再起動

[サーバーを再起動]をクリックすると、サーバーを再起動することができます。



E	Server	
🗐 Server		
t≣ Transfer ^	User Connections	Storage Status         Select Disk         //         V         License Information:
Transfering	Online Users Client Connections	Free79.02%  Activated (10240Mbps) Details
Transfer log Point to point tran	1 0	
Point to point log	After users connecting with Raysync Client, each connected webpage is counted as one client connection.	Used20.07%     Server Status     Free © Used     Bunning
Share Manager ^		39.49 GB free of 49.98 GB
Invitation upload		
Share download	Main Information Modify	CPU Into
Email	Server Name: Raysync server	© CPU Usage (%)
■ Users Manager ^	Version: 5.0.5.8	45
Users	MAC Address: 00:50:56:8a:27:e8	40
Operation records	OS: Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Care-x86_64	30
User group	Host :	20
Third-party auth	UDP Port: 32001	15
Auth A/C setting	UDP Package Size: 1200	5
Space statistics	Compression 10: Enabled	¢ O
Send notification	Bandwidth: 0	
Storage config	License:	NIC Info Select Network Card: docker0 V
Advanced Setting ~		
Personalization	🖒 Shutdown server 🖉 🧭 Reboot server	1.0 Outgoing Speed (Mttps) Outgoing Speed (Mttps)

# 2.3.4 サーバーの停止

[サーバーを停止]をクリックすると、サーバー転送サービスが停止し、Web サービスは通常通り に動作します。

Server	Server				
≣ Transfer ^	User Connection	ns	Storage Status	Select Disk: 📝 👻	License Information:
Transfering	Online Users	Client Connections	Free75	0.02%	Activated (10240Mbps)     Details
Transfer log	1	0			
Point to point tran		0			Server Status
Point to point log	After users conner counted as one cli	cting with Raysync Client, each connected webpage is ient connection.		Free Used	Running
👂 Share Manager 🛛 🔨				39,49 GB free of 49,98 GB	
Invitation upload					
Share download	Main Informa	Modify Modify	CPU Info		
Email	Server Name:	Raysync server	50	CPI	U Usage (%)
🗈 Users Manager \land	Version:	5.0.5.8	45		Â
Users	MAC Address:	00:50:56:8a:27:e8	40 35		
Operation records	OS:	Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	30		
User group	Host 💽:	121.201.121.155	20		
Third-party auth	UDP Port:	32001	15		
Auth A/C setting	UDP Package Si	ze: 1200	5		
Space statistics	Compression ()	t Enabled	<sup>6</sup>		0
Send notification	Bandwidth:	0			
Storage config	License:	DBHK4FKZFAZFBYZV	NIC Info		Select Network Card: docker0 🗸
Advanced Setting ~					
Personalization	0 :	Shutdown server 🖒 Reboot server	1.0	Incoming Speed (Mbp:	s) 🛑 Outgoing Speea (Mops)

# 2.3.5 サーバーの起動

サーバーが停止状態の場合は、「サーバーを起動」をクリックしてサーバーを起動します。



	Server		
E Transfer	User Connections	Storage Status Salert Dide	. The second s
1 Transfering Transfering Point to point tran Point to point log	Online Users Client Connections           1         0           After users connection with Rarvarc Client such connected websage is	Free79.02%	License Information:  Activated (10240Mbps)  Details  Server Status
🔗 Share Manager \land	counted as one client connection.	Free Used 39.49 GB free of 49.98 GB	Not Running
Invitation upload Share download	Main Information Medify	CPU Info	
Email	Server Name: Raysync server	35	9U Usage (%)
🚉 Users Manager 🛛 🔺	Version: 5.0.5.8	30 1 1	
Users	MAC Address: 00:50:56:8a:27:e8	25 and I have have a	
Operation records	OS: Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	20	
User group	Host 0:	15	
Third-party auth	UDP Port: 32001	10	
Auth A/C setting	UDP Package Size: 1200	5	
Space statistics	Compression 1: Enabled	ê	0
Send notification	Bandwidth: 0		
Storage config	License:	NIC Info	Select Network Card: docker0 🗸
	O Start server	1.0 Incoming Speed (Mb)	ss) 🔴 Outgoing Speed (IMops)

# 2.3.6 管理者コンソールのログアウト

ユーザー名をクリックしてオプションを展開し、[終了]をクリックします。

≡ ⊟ Server	Server					C Account Settings
t≣ Transfer ^	User Connection	15	Storage Status	Select Disk: / 🗸	License Information:	O Log Out
Transfering	Online Users	Client Connections	Free79.02%		• Activated (10240Mbps)	Details
Transfer log Point to point tran	1	0				
Point to point log	After users conner counted as one cli	cting with Raysync Client, each connected webpage is ient connection.	Fi	Used20.97%	Running	
🔗 Share Manager 🛛 🗠			39.49 GB	free of 49.98 GB		
Invitation upload Share download	Main Informa	ation Modify	CPU Info			
Email	Server Name:	Raysync server		•	CPU Usage (%)	
🖬 Users Manager \land	Version:	5.0.5.8	45	Â		
Users	MAC Address:	00:50:56:8a:27:e8	40 35			0
Operation records	OS:	Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4. 1708-Care-x86_64	30	harrison	~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~	m
User group	Host 🖲:		20			
Third-party auth	UDP Port:	32001	15			
Auth A/C setting	UDP Package Si	ze: 1200	5			

# 2.4 サーバー有効化

Raysync サーバーのライセンスが有効化された後、最高の速度を手に入れることができます。ラ イセンスが有効化されていない場合、デフォルトは 5Mbps の帯域幅です。

# 2.4.1 オンライン有効化

ログイン後、オンラインでの有効化をお勧めします。[有効化]ボタンをクリックします。



SRaysync Admin	Console		admin ~
드 Berver	Server		
t Transfer ^ Transfering Transfer log Point to point tran	User Connections Online Users Client Connections O O	Storage Status Used/86.41%	License Information: • Inactivated (Default bandwidth SMbps) Activate Server Status
Point to point log Point to point log Point to point log Invitation upload Share download	After users connecting with Raypye Client, each connected webpage is counted as one client connection.           Main Information         Modify	Free JSN	Rutning
Email	Server Name: Raysync Server Version: 5.0.5.8	100	CPU Usage (%)
Users Operation records	MAC Address: 94:dei80:62:6c:da OS:	80 70 60	
User group Third-party auth	Host <b>B</b> UDP Port: 32001	40 30 20	
Auth A/C setting	UDP Package Size: 1200	10	

ライセンス情報に有効化コードを記入します。

Raysync Admin			
E	Server		
E Server			
t≣ Transfer ^	User Connections	Activate × License Inform	nation:
Transfering	Online Users Client Connections	License:   Inactivated ()	Default bandwidth SMbps ) Activate
Transfer log	0 0	Cancel Activate	
Point to point tran	0	Server Status	
Point to point log	After users connecting with Raysync Client, each connected webpage is counted as one client connection.	Free3.58%	
🔗 Share Manager 🛛 🗠		8.35 GB free of 232.83 GB	
Invitation upload			
Share download	Main Information Modify	CPU Info	
Email	Server Name: Raysync Server	CPU Usage (%)	
🚉 Users Manager 🛛 🗠	Version: 5.0.5.8	90	$\sim$
Users	MAC Address: 94/de/80/62/6c/da	80 70	
Operation records		60	
User group	Host :	40	
Third-party auth		30 20	

### サーバーを再起動して有効にします

	n Console	) Restarting	admin ~
E	Server		
Server			
1≣ Transfer ^	User Connections	Storage Status Select Disks F v Lice	ense Information:
Transfering	Online Users Client Connections	• In	activated ( Default bandwidth 5Mbps ) Activate
Transfer log	0 0		
Point to point tran	0	Sar	ver Status
Point to point log	After users connecting with Raysync Client, each connected webpage is counted as one client connection.	Free3.58%	Running
🔗 Share Manager \land		8.35 GB free of 232.88 GB	
Invitation upload			
Share download	Main Information Modify	CPU Info	
Email	Server Name: Raysync Server	90 . OPU Usage	(%)
🛋 Users Manager \land	Version: 5.0.5.8	80	Î
Users	MAC Address: 94:de:80:62:6::da	70 60 <b>3 (</b> )	
Operation records	OS:	50	$\sim$
User group	Host 🕒:	40	
Third-party auth	UDP Port: 32001	20	
Auth A/C setting	UDP Package Size: 1200	10	

有効化成功





#### ライセンス情報を確認

😴 Raysync Enterpl			dmin ~
5	Server		
🗐 Server			
t≣ Transfer ×	User Connections	License Information:	
Transfering	Online Users Client Connections	License:  Authorized Volume:	
Transfer log	1 1	Left Volume: User Limit:1000	
Point to point tran	· ·	Activation Date: Thu Jul 30 20:01:01 2020 Expiry Date: Tue Jan 26 20:01:01 2021	
Point to point log	After users connecting with Raysync Client, each connected webpage is counted as one client connection.	Max Bandwidth: 10240Mbps Server status	
P Share Manager -		OK	
Invitation upload			
Share download	Main Information Modify	CPU Info	
Email	Server Name: Raysync server	CPU Usage (%)	
🙉 Users Manager 🗠	Version: 5.0.5.8	25 Λ	
Users	MAC Address: 00:50:56:8a/27/e8	30	
Operation records	OS: Linux-3.10.0-327.e17.885_64-w85_64-with-centor-7.4.1 706-Core-x86_64	Barrow May and Marrow and Ma	
User group	Host O		
Third-party auth			
Auth A/C setting	UDP Package Size: 1200		

# 2.4.2 オフライン有効化(windows)

1、[Raysync ライセンス]を起動、 ①[ライセンス操作]をクリック、②[リクエストファイルの 生成]をクリック、③ライセンスを記入します。



License oper	ration Refresh	~	Remove License
License Code	Operation	0	Bandwidth(Mbps
	Generate license reques	t file	
	Please input license code	>	<
		3	
	Get license code from raysync support		
			_

2、[.req]ファイルが生成されます。これはオフラインの有効化認証リクエストファイルであり、 Raysync に送信してください。

1				Save As					x
📵 🕫 ד 🌔 🕲	▶ Thi	s PC 🔸 Local Disk (C:)	► Users ► Administrato	r 🕨 Documents		~ C	Search Documents		P
Organize 👻 New fo	older							•	0
<ul> <li>☆ Favorites</li> <li>■ Desktop</li> <li>Downloads</li> <li>③ Recent places</li> </ul>	^	Name	•	Date modified	Type	Size			
This PC Desktop Documents Downloads Music Pictures Videos Local Disk (C:)	=								
Save as type:	N552II Reque	ZZTCAZFBOPO.req st File(*.req; *.request)							>
) Hide Folders							Save	Cancel	

3、そして、Raysyn から[2020-5-25 Update.upd]のようなオフライン有効化認証ファイルが送信 されます。それを入力してください。①[ライセンス操作]をクリックし、②[更新ファイルの入 力]をクリックしてください。



4、Raysync[2020-5-25 Update.upd]からオフラインの認証ファイルを選択してください。

2		Open		X
🍥 🍥 = 🛧 🔳 Desktop	•		× ¢	Search Desktop
Organize 👻 New folder				
☆ Favorites ■ Desktop	Administrator	This PC		Libraries
Downloads     Recent places	Network	1	IL	RaySync-3.4.4.8-7011-win32
This PC Cosktop Documents Downloads Music Pictures Videos Local Disk (C;)	RaySync-5.0.1.8-7283-Pro-win32	2020-5-25 Update(1).upd UPD File 807 bytes		
🙀 Network ाम्म tsclient				
File name	2020-5-25 Update(1).upd		~	Update File(*.upd;*.update) v Open Cancel

5、[Authorization success]が表示されます。



License operation	Refresh		
License Code	Operation		
15521ZZTCAZFBOPO		Raysync license tool X	
		Authorization success	
		ok	

6、オフライン有効化認証後のインターフェースは以下のように表示します。

License Code	Exipre Date	State	Max Client Num	Bandwidth(Mbps)
552IZZTC	2020-06-30 23:59:59	Normal	10	10240

7、ファイル[Raysync (windows)のクイックガイド]の手順に従ってサーバーをデプロイして使用 してください。

# 2.5 サーバー情報の編集

サーバー情報には、サーバーアドレス、UDP 加速ポート、UDP パケットサイズ、デフォルトストレージパス、エグレス帯域幅、転送サービス、圧縮の有効性が含まれます。

サーバー情報の修正ボタンをクリックすることで、サーバー情報を編集することができます。



😂 Raysync Enterpr	İSƏ 🛛 Admin Console	e			admin v
⊑ ⊟ Server	Server				
t≣ Transfer ^	User Connection	15	Storage Status	Select Disk: 🛛 🗸 🗸	License Information:
Transfering	Online Users	Client Connections	Free79.02%		Activated (10240Mbps)     Details
Transfer log Point to point tran	1	1			
Point to point log	After users connect	ting with Raysync Client, each connected webpage is		Used20.97%	Server Status
& Share Manager ^	Share Manager		39.49 GB	Running	
Invitation upload					
Share download	Main Informat	tion Modify	CPU Info		
Email	Server Name:	Raysync server	10	🔵 c	CPU Usage (%)
🖦 Users Manager 🛛 🔺	Version:	5.0.5.8	30		A man man
Users	MAC Address:	00:50:56:8a:27:e8	25		Arres and a second
Operation records	OS:	Linux-3.10.0-327.e17.x86_64-x86_64-with-centos-7.4. 1708-Core-x86_64	20		
User group	Host 💽		10		
Third-party auth	UDP Port:	32001	5		
Auth A/C setting	UDP Package Siz	ze: 1200	0		
Space statistics	Compression ():	Enabled			0

# 2.5.1 サーバーアドレス

- サーバーアドレスは、IPアドレスまたは関連するドメイン名に変更することができます。
- サーバーにドメイン名でアクセスする必要がある場合は、ドメイン名に変更します。
- 内部ネットアドレスでサーバーにアクセスする必要がある場合は、内部ネットアドレスに変 更します
- 外部ネットアドレスでサーバーにアクセスする必要がある場合は、外部ネットアドレスに変更します
- サーバーアドレスが変更された後、フロントエンドとバックグランド両方の管理者は、新しいサーバーアドレスでアクセスする必要があります

Skaysync Enterpr	158 Admin Console	
Ξ	Server	
Server	Jerver	
1≣ Transfer ∧	User Connections	License Information:
Transfering	Online Users Client Connections	Server Name  Activated (10240Misps)  Details
Transfer log	1 1	Kalysync server Host Support domain and IP address
Point to point tran		
Point to point log	After users connecting with Raysync Client, each connected webpage is	UDP Port Server Status 32001
		UDP Package Size 600 - 1442
Invitation upload		1200 Outbound Bandwidth Milver Sat Der net zah bandwidth limit dear net tale.
Share download	Main Information Modify	effect
Email	Server Name: Raysync server	Ucense CPU Usage (%)
🚉 Users Manager \land	Version: 5.0.5.8	
Users	MAC Address: 00:50:56:8a:27:e8	
Operation records	OS: Linux-3:10.0-327.el7.x86_64-x86_64-with-centos-7:4.1 708-Core-x86_64	Cancel OK
User group	Host 🕘.	20
Third-party auth	UDP Port: 32001	

# 2.5.2 UDP 加速ポート

UDP ポートは、1~65535 の間のポートに変更することができます。デフォルトは 32001 です。サ ーバーのファイアウォールが既に UDP ポートを所有していることを確認する必要があります。さ もなければ、転送が失敗します。変更後、サーバーを再起動する必要があります。



🗧 Raysync Enterp	r <b>ise</b>   Admin Console	2				1	admin ~
E	Server						
E Server	Server						
t≣ Transfer ^	User Connection	5	Edit	~		License Information:	
Transfering	Online Users	Client Connections	Server Name	.		Activated (10240Mbps)	Details
Transfer log Point to point tran	1	1	Kaysync server Host Support domain and IP address				
Point to point log	After users connec counted as one clie	ting with Raysync Client, each connected webpage is ent connection.	UDP Port 32001			Running	
🔗 Share Manager 🗠 🗠			UDP Package Size 600 ~ 1442				
Invitation upload			Outbound Bandwidth Mbps Set 0 or not set, bandwidth limit does not take	1			
Share download	Main Informa	tion Modify	effect 0	18			
Email	Server Name:	Raysync server	License			sage (%)	
🖦 Users Manager 🗠	Version:	5.0.5.8		- 1		8 8	
Users	MAC Address:	00:50:56:8a:27:e8	Compression V			$\Lambda$	
Operation records		Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4.1 708-Core-x86_64	Cancel	κ.	And	1 have been have	
User group	Host 🕒		20				
Third-party auth	UDP Port:						
Auth A/C setting	UDP Package Siz	e: 1200					
Space statistics	Compression 🖲	Enabled					

# 2.5.3 UDP メッセージサイズ

UDP メッセージのサイズは通常、デフォルト値よって設定されます。デフォルトは1200 です(範囲は600~1442)。

🗧 Raysync Enterpr		
Ξ	Common	
Server	Seivei	
t≣ Transfer ^	User Connections	Edit × License Information:
Transfering	Online Users Client Connections	Server Name  Activated (10240Mbps) Details
Transfer log	1 1	Najvjini. vervet Host Support domain and IP address
Point to point tran		
Point to point log	After users connecting with Raysync Client, each connected webpage is counted as one client connection.	32001 Server Status
🔗 Share Manager \land		UDP Package Size 600 ~ 1442
Invitation upload		Outbound Bandwidth Mbps Set 0 or not set, bandwidth limit does not take
Share download	Main Information Modify	effect 0
Email	Server Name: Raysync server	License CPU Usage (%)
🖦 Users Manager 🛛 🔺	Version: 5.0.5.8	Compression (
Users	MAC Address: 00:50:56:8a:27:e8	
Operation records	OS: Linux-3.10.0-327.e17.x86_64-x86_64-with-centos-7.4.1 708-Care-x86_64	Cancel OK
User group	Host O:	15
Third-party auth		
Auth A/C setting	UDP Package Size: 1200	
Space statistics	Compression : Enabled	e e e e e e e e e e e e e e e e e e e

# 2.5.4 圧縮を有効化

圧縮を有効にすれば、圧縮可能なファイルを圧縮して転送することで、帯域の使用量を減らし、 転送効率を向上させることができます。



😂 Raysync Enterpr	ISE   Admin Console	2		admin 🗸
E	Sonyor			
Server	Jerver			
t≣ Transfer ^	User Connection	\$	Edit × Ucense Information:	
Transfering	Online Users	Client Connections	Server Name  Activated (10240Mbps)	Details
Transfer log	1	1	Host Support domain and IP address	
Point to point tran	1.1			
Point to point log	After users connec counted as one clip	ting with Raysync Client, each connected webpage is ent connection.	UDP Port Server Status 32001	
🔗 Share Manager 🗠 🗠			UDP Package Size 600 ~ 1442	
Invitation upload			1200 Outbound Bandwidth Mbps Set 0 or not set, handwidth limit does not take	
Share download	Main Informa	tion Modify	offect	
Email	Server Name:	Raysync server	License OPU Usage (%)	
🚉 Users Manager \land		5.0.5.8		
Users	MAC Address:	00:50:56:8a:27:e8		
Operation records		Linux-3.10.0-327.el7.x86_64-x86_64-with-centos-7.4.1 708-Core-x86_64	Cancel OK	~
User group	Host 0:		20	
Third-party auth				
Auth A/C setting	UDP Package Siz	e: 1200		
Space statistics	Compression 🕢	Enabled		

# 2.6 転送情報

ユーザーが転送している、または転送したファイルの情報は、転送情報から確認することができ ます。

# 2.6.1 ライブ転送

転送を入力すると、タスク情報を表示させることができます:ユーザー名、ユーザーソース IP、 ファイルタイプ、ファイル名、国、地域、都市、転送回数、トータル速度など。

S Raysync Enter	prise   Control Center									admin
Ξ Server	Current transfers									
t≣ Transfer ^	Total transfer files:1 Tota	al transmission speed:66.77 N	Vibps							
Current transfers	Account	IP	Туре	Taskname	Country	Region	City	Total transmission	Total transmission speed	Actions
Transfer log	test		Download	RaySync-5.0.3.9-7904-Pro.tar.gz	1.			1	66.77 Mbps	Details   Stop
Invitation upload										
Share download										
Email										
Users										
Operation records										
User group Third-party authe										
Space statistics										
⊜ Storage Configura										
Advanced Setting ~										

# 2.6.2 転送ログ

ユーザーが転送したファイルの情報は、転送ログから確認することができます。



aysync Enterp	orise   Control Center				a
er	Transfer log				
isfer 🔹 🔨	User :	Start time 2020-06-20 🗇 End time 2020-07-20 🗇 Search	Download Download All		
sfer log	Users \$	File	Bytes	Time 0	Actions
e Manager 🛛 🔨	test	test_20200717203400240.log	28.79 MB	2020/07/17 20:34:00	View   Download
ation upload	test .	test_20200717220810890.log	295 B	2020/07/17 22:08:10	View   Download
e download	test	test_20200719163530730.log	283 B	2020/07/19 16:35:30	View   Download
rs Manager 🛛 🗠	🗌 test	test_20200719163552752.log	283 B	2020/07/19 16:35:52	View   Download
5	test	test_20200720045124884.log	335 B	2020/07/20 04:51:24	View   Download
ration records	🗌 test	test_20200720121409449.log	28.79 MB	2020/07/20 12:14:09	View   Download
i-party authe	test	test_20200720121418458.log	284 B	2020/07/20 12:14:18	View   Download
e statistics	🗌 test	test_20200720202742062.log	159 B	2020/07/20 20:27:42	View   Download
age Configura					Page1-8/Total8 < 🚹 🖂 10.
inced Setting ~	L				

#### [表示]をクリックすると、オンライン状態でログを確認できます。

Ξ	Transfer	log																								
Server			1.	Log view :test	_20200720121	418458.log							0×													
Current transfers			Start time 2020-0	Туре	File Name	Client ip	Bytes	Start time	End time	Time	Transfer size	Target size	Average speed													
Transfer log		Users ¢	Fil	Upload	/linux-3.4.113/	172.16.4.52	700.00 MB	2020-07-19 20:33:02	2020-07-19 20:36:07	3minutes5seco	700.00 MB	700.00 MB	30.15 Mbps				Action	Actions	Actions	Actions	Actions	Actions	Actions	Actions	Actions	Actions
🔗 Share Manager 🛛 🔺		test	te:	Unload	/linux-3.4.113/	172 16 4 52	11178	2020-07-19 20-88-02	2020-07-19 20 33:02	Orecondr	11178	111/8	68.01 Kbar						View   Download	View   Download						
Invitation upload		test	te:	0,000	re	112.10.00	1.1110	2020 07 15 20 33 02	2020 01 13 203302	0.000.000		1.11 1.4					View	View   Dowr	View   Download	View   Download						
Email		test	te	Upload	block/blk-cgro up.h	172.16.4.52	11.28 KB	2020-07-19 20:33:02	2020-07-19 20:33:02	Oseconds	11.28 KB	11.28 KB	851.05 Kbps				View	View   Dowr	View   Download	View   Download						
⊒⊾ Users Manager 🔹 🗠		test	te:	Upload	/linux-3.4.113/ block/blk-cgro	172.16.4.52	42.98 KB	2020-07-19 20:33:02	2020-07-19 20:33:02	Oseconds	42.98 KB	42.98 KB	1.22 Mbps				View	View   Dowr	View   Download	View   Download	View   Download	View Download	View   Download	View   Download	View   Download	View Download
Users		test	tes	Uniord	/linux-3.4.113/	172 16 4 52	52 20 VP	2020-07-10 20-22-02	2020-07-19 20 22 02	Orecoods	52 20 VD	52 20 VD	417.01 Mber				View	View   Dowr	View   Download	View   Download						
Operation records		test	te	opolad	e	174-10-6-24	33.30 Kg	2020-07-19 2033.02	2020-07-19-20-3302	orecondar.	33.50 10	33.50 10	HILDI MODE				View	View   Dowr	View   Download	View   Download						
Third-party authe		test	te	Upload	/linux-3.4.113/ +5111/.mailma p	172.16.4.52	4.83 KB	2020-07-19 20:33:02	2020-07-19 20:33:02	Oseconds	4.83 KB	4.83 KB	37.77 Mbps				View	View   Dowr	View   Download	View   Download						
Space statistics		test	te:	Upload	/linux-3.4.113/ +5111/Kbuild	172.16.4.52	2.48 KB	2020-07-19 20:33:02	2020-07-19 20:33:02	Oseconds	2.48 KB	2.48 KB	19.35 Mbps							View   Download	View   Download					
😝 Storage Configura				Upload	/linux-3.4.113/ block/blk-flush.	172.16.4.52	13.09 KB	2020-07+19 20:33:02	2020-07-19 20:33:02	Oseconds	13.09 KB	13.09 KB	969.40 Kbps		Page1-8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8	Page1-8/Total8 💽 🚺 💽 10/pag	Page1-8/Total8 🔄 🚺 🛒 10/pag
Advanced Setting ~					c /linux-3.4.113/																					
				Upload	+5111/MAINT AINERS	172.16.4.52	286.40 KB	2020-07-19 20:33:02	2020-07-19 20:33:02	Oseconds	286.40 KB	286.40 KB	8.71 Mbps													
					2 3 4	5	1747																			

#### [ダウンロード]をクリックすると、ログをダウンロードして確認できます。

😂 Raysync Enter	prise   Control Center				admin
드 Server	Transfer log				
t≣ Transfer ^ Current transfers	User :	Start time 2020-06-20 🗇 End time 2020-07-20 🗂 Se	arch Download Download All		
Transfer log	Users \$	File	Bytes	Time \$	Actions
🔗 Share Manager 🛛 🦒	test	test_20200717203400240.log	28.79 MB	2020/07/17 20:34:00	View   Download
Invitation upload Share download	test	test_20200717220810890.log	295 B	2020/07/17 22:08:10	View   Download
Email	test t	test_20200719163530730.log	283 B	2020/07/19 16:35:30	View   Download
🚉 Users Manager 🔷 🗠	test	test_20200719163552752.log	283 B	2020/07/19 16:35:52	View   Download
Users	test	test_20200720045124884.log	335 B	2020/07/20 04:51:24	View   Download
Operation records	test	test_20200720121409449.log	28.79 MB	2020/07/20 12:14:09	View   Download
Third-party authe	test	test_20200720121418458.log	284 B	2020/07/20 12:14:18	View   Download
Space statistics	<ul> <li>test</li> </ul>	test_20200720202742062.log	159 B	2020/07/20 20:27:42	View   Download
😝 Storage Configura					Page1-8/Total8 ( 1 ) 10/page v
Advanced Setting ~					
Personalization					

ユーザー名、ログの開始時刻と終了時刻を検索することができます。



😂 Raysync Enter	prise   Control Center					ldmin
드 B Server	Transfer log					
j≣ Transfer ^	User :	Start time 2020-06-20 🗇 End time 2020-07-20 🗇 S	Search Download Download All			
Current transfers						
Transfer log	Users \$	File	Byt	es Time ‡	Actions	
🔗 Share Manager \land	test	test_20200717203400240.log	28.	79 MB 2020/07/17 20:	34:00 View   Download	
Invitation upload	test	test_20200717220810890.log	295	B 2020/07/17 22;	08:10 View   Download	
Email	🗌 test	test_20200719163530730.log	28	B 2020/07/19 16:	35:30 View   Download	
🛃 Users Manager 🗠	test	test_20200719163552752.log	283	B 2020/07/19 16:	35:52 View   Download	
Users	🗌 test	test_20200720045124884.log	335	B 2020/07/20 04:	S1:24 View   Download	
Operation records	test	test_20200720121409449.log	28:	79 MB 2020/07/20 12:	14:09 View   Download	
Third-party authe	test	test_20200720121418458.log	284	B 2020/07/20 12:	14:18 View   Download	
Space statistics	🗌 test	test_20200720202742062.log	155	B 2020/07/20 20:	27:42 View   Download	
Generation Storage Configura					Page1-8/Total8 🔄 🚺 🔉 10/	'page v
Advanced Setting ~						
Personalization						

# 2.6.3 ポイントツーポイント転送

ポイントツーポイント転送を入力すると、アカウント、IP、タスク名、受信者 ID、合計ファイル、速度、操作に関する情報が表示されます。

S Raysync Emerph	Admin Console						admin v
Ξ	Point to point transfe	ring					
Server							
t≣ Transfer ^	Total transfer files: 1	Total transmission spe	ed: 10.28 Mbps				
Transfering	Account	IP	Task name	Receiver ID	Total transmission	Transmission speed	Actions
Transfer log	, account			incluter to		Transmission specie	
Point to point tran	test	10.51.96.152	1G.txt	6075461186	1	10.28 Mbps	Details   Stop
Point to point log							
📌 Share Manager 🗠 🗠							
Invitation upload							
Share download							
Email							
🚉 Users Manager 🗠							
Users							

[詳細]ボタンをクリックすると、ポイントツーポイントのタスクファイル名、サイズ、速度を確認できます。

S Raysync Enterpl								admin ~
Ξ	Point to point transfe	ring						
E Server				Transport taskTest		×		
t≣ Transfer ^								
Transfering	Account	IP	Task name	File Name	Size	Speed	Transmission speed	Actions
Transfer log				1.5G.txt	12.13 MB	25.36 Mbps		
Point to point tran	test	172.16.4.52		100M.bxt	0 B	0.00 bps		Details   Stop
Point to point log				1G.txt	18.56 MB	38.52 Mbps		
Chara Managar				200M.bd	8.13 MB	17.55 Mbps		
ge Share manager				300M.txt	0 B	0.00 bps		
Invitation upload				400M.txt	2.44 MB	6.59 Mbps		
Share download				500M.bxt	4.69 MB	18.94 Mbps		
Email				600M.txt	0 B	0.00 bps		
🚌 Users Manager \land								

[停止]ボタンをクリックすると、タスクが停止します。



😂 Raysync Enterp	rise   Admin Conso	le					admin v
Ē	Point to point tran	nsfering					
Server							
t≣ Transfer ^	Total transfer files	a: 8 Total transmission s	peed: 75.56 Mbps				
Transfering						-	
- · ·	Account	IP	lask name	Receiver ID	lotal transmission	Transmission speed	Actions
Transfer log							and the second
Point to point tran	test	172.16.4.52	Test	4871521586	8	75.56 Mbps	Details Stop
Point to point log							
🔗 Share Manager \land							
Invitation upload							
Share download							

#### タスクが停止された後、「管理者によって停止されました」と表示されます。

<b>3</b> Ti	ransfer List			2	11		$\times$
	Transmission Task	Sync Task	Po	oint-t	o-Poi	nt Tas	k
	Send to ID(4871521586) Te	st (3 items)	4m 46s remaining		$\sim$	(C1)	
• (	Stopped by administrator	591.00MB/7.55GB	Sended: 0/8023	1	^		

# 2.6.4 ポイントツーポイントログ

ポイントツーポイントログを入力すると、ユーザーの転送履歴情報を確認できます。

😌 Raysync Enterp	rise   Admin Console					admin ~
E	Point to point log					
Server 🗎	-					
t≣ Transfer ^	User	Start time 2020-09-16 🖾 End time 2020-10-16 🖾	Search Download Download	All		
Transfering						
Transfer log	Users 💠	File	Size	Receiver ID	Operation time 👙	Actions
Point to point tran	test	test_20201016180658818_6075461186.log	768 B	6075461186	2020-10-16 18:22:42	View   Download
Point to point log	test	test_20201016182333813_4871521586.log	7.29 KB	4871521586	2020-10-16 18:30:55	View   Download
Invitation upload					Total2, page1/2	1 > 10/page ~
Share download						
Email						
🚉 Users Manager \land						

#### [表示]をクリックすると、オンライン状態でログを確認できます。

🗧 Raysync Enterpr	rise Ad	min Console					中文 admin ~
Ē	Point to	point log					
📑 Server							
t≣ Transfer ^	User		Start time 2020-09-16 🗇 End time 2020-10-16	Search Download Download Al	1.		
Transfering							
Transfer log		Users \$	File	Size	Receiver ID	Operation time \$	Actions
Point to point tran		test	test_20201016180658818_6075461186.log	768 B	6075461186	2020-10-16 18:22:42	View Download
Point to point log		test	tect 20201016182233813 4871521586 log	7.20 KB	4871521585	2020-10-16 18:30-55	View   Download
& Share Manager \land		1031	(31_60201010102555015_4011521500.0g	T-EU NU	4071521500	2220 10 10 10.00.00	
Invitation upload						Total2, page1/2/	1 > 10/page ~
Share download							
Email							
🚉 Users Manager 🛛 🗠							



😂 Raysync Enterpr	ise   Ad	min Console	5					Ioading seccess.							admin 🖂
⊑ ≣ Server	Point to	point log													
1 Transfer 🔶	User		Log view :test	20201016180	658818_60754	61186.log							o ×		
Transfering			Туре	File Name	Client ip	Size	Start time	End time	Receiver ID	Time	Transfer size	Target size	Average speed	_	
Transfer log		Users \$	Upload	/1G.bit	10.51.96.152	724.25 MB	2020-10-16 18:07:04	2020-10-15 18:18:01	6075461186	0 seconds	0.8	1.00 GB	0.00 bps	\$	Actions
Point to point tran			Upload	/1G.txt	10.51.96.152	992.38 MB	2020-10-16 18:20:17	2020-10-16 18:22:26	6075461186	0 seconds	0 В	1.00 GB	0.00 bps	22.42	View   Download
Point to point log			Upload	/1G.txt	10.51.96.152	1.00 GB	2020-10-16 18:22:41		6075461186	15 seconds	992.38 MB	1.00 GB	524.20 Mbps		
🔗 Share Manager 🗠														30:55	View   Download
Invitation upload														Total2, page1/2	10/page =
Share download															
Email															
🚌 Users Manager 🗠															
Users															
Operation records															
User group															
Third-party auth															
Auth A/C setting															
Space statistics															
Send notification															
Storage config			1												

# また、[ダウンロード]または[すべてダウンロード]をクリックすると、ログを確認することもできます。

😂 Raysync Enterpr	rise   Adı	min Console					admin ~
E	Point to	point log					
Server 🗎							
t≣ Transfer ^	User		Start time 2020-09-16 🗇 End time 2020-10-16	Search Download Download All			
Transfering	_						
Transfer log		Users ≑	File	Size	Receiver ID	Operation time 🌩	Actions
Point to point tran		test	test_20201016180658818_6075461186.log	768 B	6075461186	2020-10-16 18:22:42	View Download
Point to point log Point to point log		test	test_20201016182333813_4871521586.log	7.29 KB	4871521586	2020-10-16 18:30:55	View   Download
Invitation upload						Total2, page1/2	1 > 10/page ~
Share download							
Email							
■. Users Manager ^							

#### ユーザー名、ログの開始時刻と終了時刻を検索することができます。

😂 Raysync Enterpr	r <i>ise</i> Admir	n Console							admin 🗸
Ξ	Point to po	pint log							
📑 Server									
t≣ Transfer ^	User		Start time 2020-09-16	End time 2020-10-16	Search	Download Downlo	ad All		
Transfering									
Transfer log	•	Users 💠	File			Size	Receiver ID	Operation time 👙	Actions
Point to point tran		test	test_20201016180	558818_6075461186.log		768 B	6075461186	2020-10-16 18:22:42	View   Download
Point to point log		test	test_20201016182	333813_4871521586.log		7.29 KB	4871521586	2020-10-16 18:30:55	View   Download
Invitation upload								Total2, page1/2	1 > 10/page ~
Share download									
Email									
🛋 Users Manager \land									



# 2.7 リンク管理

# 2.7.1 アップロード招待

### 2.7.1.1 リンクの詳細を見る

フォルダをダブルクリックすると、リンクの詳細が表示されます。

😂 Raysync Enter	orise   Control Center				adn	in
Ē	Invitation					
Server						
t≣ Transfer ^	User : Start time 2020-06-	21 🔲 End time 2020-07-20 🗊 Status All	Search			- 1
Current transfers						
Transfer log	Disable Invitation Delete Link(s)					
6º Share Manager A	Folder	Name	Invitation time \$	Expired time \$	Status \$	
Invitation upload	□■ /	test	2020-07-19 19:17:15		Using	
Share download	Link:http://172.16.4.52:8090/share/O6m1vg	HIEFDXgJaCPSwY (Password: tMup) & Copy link				
Email	Share content: /;					
🏨 Users Manager 🛛 🗠					Page1-1/Total1 < 🚹 😕 10/pag	
Users						
Operation records						
User group						
Third-party authe						
Space statistics						
la Storage Configura						
Ø Advanced Setting ~						
O Personalization						

### 2.7.1.2 リンクをコピー

😂 Raysync Enterp	prise   Control Center				admin
E	Invitation				
Server					
l≣ Transfer ^	User : Start time 20	20-06-21 🖾 End time 2020-07-20 🖾 Status All	<ul> <li>Search</li> </ul>		
Current transfers					
Transfer log	Disable Invitation Delete Link(s)				
	Folder \$	Name	Invitation time \$	Expired time \$	Status 🛊
Invitation upload	0 = /	test	2020-07-19 19:17:15		Using
Share download	Link:http://172.16.4.52:8090/share/0	6m1vqHIEFDXgjaCPSwY (Password: tMup)			
Email	Share content: /;				
■ Users Manager ^					Page1-1/Total1 < 1 > 10/page >
Users					
Operation records					
User group					
Third-party authe					

# 2.7.1.3 リンクをキャンセル

アップロード招待インターフェースに入り、任意の共有リンクを選択し、[招待を無効にする] をクリックします。



😂 Raysync Enter	<b>Dr<i>ise</i>   Control Center</b>				admin
E	Invitation				
Server					
t≣ Transfer ^	User : Start time	2020-06-21 🗇 End time 2020-07-20 🗇 Status All	Search		
Current transfers					
Transfer log	Disable Invitation Delete Link(s)				
	✓ Folder ≑	Name	Invitation time \$	Expired time \$	Status ‡
Invitation upload	2 🖬 /	test	2020-07-19 19:17:15		Using
Share download	Link:http://172.16.4.52:8090/share/	O6m1vqHIEFDXgjaCPSwY (Password: tMup) 🖉 Copy link			
Email	Share content: /;				
🗈 Users Manager \land					Page1-1/Total1 C 1 > 10/page V
Users					
Operation records					
User group					
Third-party authe					
Space statistics					

# 2.7.1.4 リンクを削除

アップロード招待インターフェースに入り、任意の共有リンクを選択し、[招待を削除する]をク リックします。

😂 Raysync Enter	<b>prise</b>   Control Center				admin
E	Invitation				
Server					
t≣ Transfer ^	User : Start time 2020-06-21	End time 2020-07-20	v Search		
Current transfers					
Transfer log	Disable Invitation Delete Link(s)				
	☑ Folder ‡	Name	Invitation time \$	Expired time \$	Status ¢
Invitation upload	🛛 🖬 /	test	2020-07-19 19:17:15		Using
Share download	Link:http://172.16.4.52:8090/share/O6m1vqHIEF	OXgjaCPSwY (Password: tMup) & Copy link			
Email	Share content: /;				
👥 Users Manager \land					Page1-1/Total1 < 1 > 10/page >
Users					
Operation records					
User group					

# 2.7.1.5 検索

ユーザー、開始時刻、終了時刻、状態での検索に対応しています。

😂 Raysync Enterp	orise   Control Center				admin
≘ ≣ Server	Invitation				
f≣ Transfer ^ Current transfers	User : Start time 2020-06-21	End time 2020-07-20 Status All	<ul> <li>✓ Search</li> </ul>		
Transfer log	Disable Invitation Delete Link(s)				
🔗 Share Manager \land	🗆 Folder \$	Name	Invitation time \$	Expired time \$	Status \$
Invitation upload	□ <b>■</b> /	test	2020-07-19 19:17:15		Using
Share download	Link:http://172.16.4.52:8090/share/O6m1vgHIEFE	XgjaCPSwY (Password: tMup) 2 Copy link			
Email	Share content: /;				
🖦 Users Manager 🗠					Page1-1/Total1 < 1 > 10/page >
Users					
Operation records					
User group					
Third-party authe					
Space statistics					



# 2.7.2 ダウンロードの共有

# 2.7.2.1 リンクの詳細を見る

フォルダをダブルクリックすると、リンクの詳細が表示されます。

😂 Raysync Enter	prise   Control Center				admin	
⊑ ⊜ Server	Share download					
t≣ Transfer ^	User : Start time 2020-0	6-23 🗇 End time 2020-07-22 🗇 State	us All ~ Search			
Current transfers						
Transfer log	Disable Share Delete Link(s)					
🔗 Share Manager \land	🗆 File 💠	Name	Share time \$	Expired time \$	Status \$	
Invitation upload	🗌 🚞 New Folder	⊘ 💼 test	2020-07-20 15:52:31		Using	
Share download	Link:http://172.16.4.52:8090/share/716	OFbWKpdQSRrgsLzB8 (Password: CgEq) & Copy	link			
Email	Share content: /New Folder;					
🚉 Users Manager \land					Page1-1/Total1	
Users						
Operation records						
User group						

#### 2.7.2.2 リンクをコピー

😂 Raysync Enter	<b>prise</b>   Control Center				admin
⊑ ⊜ Server	Share download				
	User : Start time z	020-06-23 🗇 End time 2020-07-22 🗇 Stat	tus All		
	Disable Share Delete Link(s)				
	🗌 File 单	Name	Share time \$	Expired time \$	Status ‡
Invitation upload	🗌 🧮 New Folder	⊘	2020-07-20 15:52:31		Using
Share download	Link:http://172.16.4.52:8090/share	e/7I6OFbWKpdQSRrgsLzB8 (Password: CgEq)	y link		
	Share content: /New Folder;				
💵 Users Manager \land					Page1-1/Total1 C 1 > 10/page ~
Operation records					

### 2.7.2.3 リンクを無効にする

ダウンロードの共有インターフェースに入り、任意の共有リンクを選択し、[共有を無効にする] をクリックします。

😁 Raysync Enter	<b>prise</b>   Control Center					admin
⊑ ⊜ Server	Share download					
t≣ Transfer ^	User : Start time 2020-06	23 🗊 End time 2020-07-22 🗊 Status	All × Search			
Current transfers						
Transfer log	Disable Share Delete Link(s)					
Share Manager ^	✓ File \$	Name	Share time \$	Expired time \$	Status ‡	
Invitation upload	🔽 🧮 New Folder	test	2020-07-20 15:52:31		Using	
Share download	Link:http://172.16.4.52:8090/share/7160	FbWKpdQSRrgsLzB8 (Password: CgEq) & Copy lin	<			
Email	Share content: /New Folder;					
🛋 Users Manager 🗠					Page1-1/Total1 < 🚹 🖂	10/page v
Users						
Operation records						

🛞 Website: www.raysync.io 🛛 🗞 Tel: +86 18681593969

Email:support@raysync.io



# 2.7.2.4 リンクを削除

ダウンロードの共有インターフェースに入り、任意の共有リンクを選択し、[リンクを削除する] をクリックします。

GRaysync Enterprise   Control Center admin									
Ξ	Share download								
Server									
t≣ Transfer ^	User : Start time 2020-08-23 🗆 End time 2020-07-22 💼 Status All 🗸 Search								
Current transfers									
Transfer log	Disable Share Delete Link(s)								
Share Manager ^	▼ File \$	Name	Share time \$	Expired time \$	Status ≑				
Invitation upload	🗹 🧮 New Folder	test	2020-07-20 15:52:31		Using				
Share download	Linkhttp://172.16.4528090/share/7/60FbWKpdQsRrgsLz88 (Password: CgEq) & Copy link								
Email	Share content: /New Folder;								
■ Users Manager ^					Page1-1/Total1 ( 1 ) 10/page ~				
Users									
Operation records									

# 2.7.2.5 検索

Raysync Enter	<b>prise</b>   Control Center				admin			
Server	Share download							
Transfer ^	User : Start time 2020-06-	23 🔲 End time 2020-07-22 🔲 Statu	us All × Search					
	Disable Share Delete Link(s)							
Share Manager 🔨 🔨	☑ File \$	Name	Share time \$	Expired time \$	Status 🗘			
Invitation upload	New Folder	test	2020-07-20 15:52:31		Using			
	Linkhttp://72.164.528090/share/7/60FbWkpdQsRrgsLzB8 (Password: CgEq)							
	Share content: /New Folder;							
					Page1-1/Total1 < 1 > 10/page ~			

# 2.7.3 メールアドレスの設定

ダウンロード、アップロード招待を共有する場合のメールサーバーの設定(主流のメールアドレスに対応しています): Gmail、AOL、iCloud、MSN、Microsoft365、Outlook、Hotmail、Live、yahoo、など)



😂 Raysync Enter	<b>prise</b>   Control Center		
Ξ	Email		
🛱 Server			
1≣ Transfer ^	* Sender nickname	tart	
Current transfers	Schoel mexicane	test	
Transfer log	* Sender Email	test@outlook.com	
A Share Manager	* Email provider	Microsoft365	~
	* SMTP Host	smtp.office365.com	
Invitation upload	* SMTP Port	587	
Share download	* Encryption	STARTTI S	~
Email			
🛋 Users Manager 🛛 🗠	* SMTP Account	test@outlook.com	
Users	* Password		
Operation records		ОК	
User group			
Third-narty authe			
Space statistics			
Storage Configura			
Advanced Setting      ✓			
O Personalization			

# 2.8 ユーザー管理

- 2.8.1 ユーザー一覧
- 2.8.1.1 ユーザーの追加

#### [追加]をクリック

😂 Raysync Enterp	rise   Admin Console								admin ~
E	Users								
E Server									
t≣ Transfer ^	Full Name	Account	Email	9	Status All · Locked All	<ul> <li>Search</li> </ul>			
Transfering									
Transfer log	Add Import	t LDAP/AD domain account	Delete						
Point to point tran		Cull Manage	A	Con ell	Hear Crewes	Chattan	Canas Occupation	Create time	Antinue
Point to point log	10 +	Puir Ivanie	Account	Email	oser droups	status	space occupation	Create unie	Actions
🔗 Share Manager 🛛 🗠	2		test			<ul> <li>Offline</li> </ul>	0.8	2020-10-15 16:27:11	Edit   Locked   Delete
Invitation upload								Total1, page1/1	1 > 10/page ~
Share download									
Email									
🚌 Users Manager \land									
Users									
Operation records									
User group									
Third-party auth									
Auth A/C setting									

Website: www.raysync.io % Tel: +86 18681593969


SRaysync Enterprise   Admin Console				
Users > Add User				
E Server				
恒 Transfer ^ Full Name	0-32 characters			
Transfering *Account	3-30 characters.			
Transfer log * Password ⑦		Generate password		
Point to point tran				
Point to point log	Force users to chan	te password for the first	st time when they login	
& Share Manager A	-			
Invitation upload Home Directory ③				
Share download Forbidden Path ③		۲		
Email User Groups	Add			
aL Users Manager A	Default Select a	II O Reverse all		
Users	o benan o becco			
Operation records	List files	Upload file	Download file	Create directory
User group	Share	Invite	Сору	indve
Third-party auth				
Auth A/C setting Max Upload Speed ①			Mbps	
Space statistics Max Download Speed ⑦			Mbps	
Send notification	Enable			
Storage config     File Format Whitelist (?)	Enable			
Advanced Setting *	Renath is less than 255 ch			
O Personalization				
		h		
Notification Email 💿	<ul> <li>Admin setting email</li> </ul>	O User setting emai	1	
IP login whitelist 🗇	Enable	e in second second second		
	San	re		

情報を入力し、許可を与えます。

フルネーム	アカウントの本名
アカウント	作成後は変更できません
パスワード	手動または自動生成での編集できます
初回ログイン時に、パ スワードを強制的に変 更させます	有効化すると、初回ログイン後に初期パスワードを強制的に変更させま す
アクセス許可	ファイルリスト、ダウンロード、削除、名前の変更、フォルダの作成、 ファイルのアップロード、フォルダの同期
ホームディレクトリ	ホームディレクトリが設定されていない場合、ホームはシステムのデフ オルトになります。
速度制限	0に設定すると無制限になります
ユーザーグループ	1人のユーザーを複数のユーザーグループに同時に追加することができ ます



フルネーム	アカウントの本名
転送ホワイトリストの ファイル形式を開く	有効化すると、入力ボックスにファイル形式を入力します。複数の形式は「txt; iso; mp4」のように、「;」で区切る必要があります。
禁止パス	禁止するアクセスパスを設定します。ログイン後、このパスのファイル (フォルダ)を表示できません
ディレクトリの同期	有効化すると、ログイン後に同期ディレクトリタスクを作成することが できます。
メール	管理者のメール通知メッセージを受信できます。
通知メール	管理者設定メール:管理者メールから共有リンク通知が送信されます ユーザー設定のメール:ユーザーのメールから共有リンク通知が送信さ れます。ユーザーはウェブ上でメールを設定する必要があります。
IP ログインホワイトリ スト	有効化すると、ホワイトリスト内の IP アドレスのみがログインできま す。例えば、192.168.0.1 から 192.168.0.100 までの IP は、 192.168.0.[1-100].と記入することができます。

[OK]をクリックして保存します

### 2.8.1.2 ユーザーの編集

任意のユーザーを選択し、[編集]をクリックします

🗲 Raysync Enterp	rise   Ad	lmin Console									admin ~
E	lisers										
Server	_										
1≣ Transfer ^	Full	Name	Account	En	nail	Status All	~ Locked All	<ul> <li>Search</li> </ul>			
Transfering											
Transfer log	Ac	id Impo	rt LDAP/AD domain account	Delete							
Point to point tran											
Point to point log		ID ‡	Full Name	Account	Email		User Groups	Status	Space Occupation	Create time	Actions
		3		test2				<ul> <li>Offline</li> </ul>	0 B	2020-10-16 14:59:22	Edit   Locked   Delete
Invitation upload		2	test	test				• Online	0 B	2020-10-15 16:27:11	Edit   Locked   Delete
Share download										Total2, page1/2	1 > 10/page ~
Email											
🚉 Users Manager \land											
Users											
Operation records											



U		Users > Edit User					
E	Server						
1	Transfer ^	Full Name	0-32 characters				
	Transfering	*Account	test2				
	Transfer log	*Password ⑦	******	Generate password			
	Point to point tran	Email					
	Point to point log		Force users to ch	ange password for the fin	st time when they logir	n 💼	
0 <sup>60</sup>	Share Manager \land						
	Invitation upload	Home Directory ③					
	Share download	Forbidden Path ③		Ð			
	Email	User Groups	Add				
21	Users Manager \land	Permissions	🗌 Default 🧿 Selec	t all ု Reverse all			
	Users		I ist files	Inload file	Download file	Create directory	
	Operation records		Rename	Delete	Сору	Move	
	User group		Share	🔽 Invite			
	Third-party auth						
	Auth A/C setting	Max Upload Speed ③	0		Mbps		
	Space statistics	Max Download Speed ③	0		Mbps		
~	Send notification	Sync 🕐	Enable				
*	Advanced Setting	File Format Whitelist 💮	Enable				
~ 	Personalization						
U							
				11			
			-				
		Notification Email ③	<ul> <li>Admin setting em</li> </ul>	ail ု User setting ema	d		
		IP login whitelist ()	Enable				
			Prease enter the IP add and separate with (111 Such as 121 211 311 31				
				h			
				Save			

# 2.8.1.3 ユーザーのロック

ロックされていないユーザーを選択します。例えば、ユーザーテストを選択して、「ロックされ ている」をクリックします。



🕏 Raysync Enterpr	<i>ise</i>   Ad	min Console	•							admin ~
드 曰 Server	Users									
t≣ Transfer ^	Full N	Name	Account		Email	Status All ~ Locked All	<ul> <li>Search</li> </ul>			
Transfering										
Transfer log	Ad	id Impo	rt LDAP/AD domain account	Delete						
Point to point tran		ID A	Cull Name	A	[mail	User Comme	(heter	Serve Orevesting	Country Name	Antines
Point to point log		ID ÷	run Name	Account	Email	user Groups	Status	space Occupation	Create unie	Actions
🔗 Share Manager \land		3		test2			@ Offline	0.8	2020-10-16 14:59:22	Edit   Locked   Delete
Invitation upload		2	test	test			• Online	0 B	2020-10-15 16:27:11	Edit Locked Delete
Share download									Total2, page1/2	1 10/page ~
Email										
🛋 Users Manager \land										
Users										

ユーザーはロックされます。

#### 2.8.1.4 ユーザーのロックを解除する

ロックされているユーザーを選択して、例えば、ユーザーテストを選択して、「ロック解除」を クリックします。

😂 Raysync Enterpr	r <i>ise</i> Admin	Console									中文 admin >
E	Users										
E Server											
t≣ Transfer ^	Full Name	e	Account		Email	Status All	<ul> <li>Locked All</li> </ul>	<ul> <li>Search</li> </ul>			
Transfering											
Transfer log	Add	Import LE	DAP/AD domain account	Delete							
Point to point tran											
Point to point log		) ÷	Full Name	Account	Email		User Groups	Status	Space Occupation	Create time	Actions
🔗 Share Manager 🛛 🗠	3			test2				<ul> <li>Offline</li> </ul>	0 B	2020-10-16 14:59:22	Edit   Locked   Delete
Invitation upload	2		test	test				• Online	0 B	2020-10-15 16:27:11	Edit UnLock Delete
Share download										Total2, page1/2	1 > 10/page ~
Email											
■ Users Manager ^											
Users											
Operation records											

ユーザーのロックが解除されます

😂 Raysync Enterp	rise Admin Console				€Raysync Enterprise   Admin Console admin ~												
≡	Users																
Server																	
1≣ Transfer ^	Full Name	Account	Ema	il S	tatus All ~ Locked All	× Search											
Transfering																	
Transfer log	Add Import	LDAP/AD domain account	Delete														
Point to point tran																	
Point to point log	ID \$	Full Name	Account	Email	User Groups	Status	Space Occupation	Create time	Actions								
🔗 Share Manager \land	□ 3		test2			<ul> <li>Offline</li> </ul>	0 B	2020-10-16 14:59:22	Edit   Locked   Delete								
Invitation upload	2	test	test			<ul> <li>Online</li> </ul>	0 B	2020-10-15 16:27:11	Edit   Locked   Delete								
Share download								Total2, page1/2	1 > 10/page ~								
Email																	
a. Users Manager ∽																	

#### 2.8.1.5 検索

ユーザーが多い場合は、右上の検索ボックスを使って、ユーザーの名、アカウント、メールアド レス、ログイン状態、ロック状態からユーザーを検索することができます。



😂 Raysync Enterpr	ise Adn	nin Console									admin ~
⊑ ■ Server	Users										
t≣ Transfer ^	Full N	lame	Account	Ema		Status All	~ Locked All	- Search			
Transfering											
Transfer log	Add	i Import Ll	DAP/AD domain account								
Point to point tran		-	-								
Point to point log		ID ÷	Full Name	Account	Email		User Groups	Status	Space Occupation	Create time	Actions
🔗 Share Manager 🛛 🧄		3		test2				<ul> <li>Offline</li> </ul>	0 B	2020-10-16 14:59:22	Edit   Locked   Delete
Invitation upload		2	test	test				Online	0 B	2020-10-15 16:27:11	Edit   Locked   Delete
Share download										Total2, page1/2	1 10/page ~
Email											
🚉 Users Manager 🗠											
Users											
Operation records											
User group											

### 2.8.1.6 LDAL/AD ドメインアカウントのインポート

[LDA/AD ドメインアカウントのインポート]をクリックすると、[サードパーティ auth]で [LDAP/AD doman]を設定した後に、ドメインサーバーで作成されたすべてのドメインユーザーア カウントが自動的にインポートされます。

😂 Raysync Enterp	rise   Admin Console									admin v
드 目 Server	Users									
t≣ Transfer ^	Full Name	Account	Emai		Status All	<ul> <li>Locked All</li> </ul>	<ul> <li>Search</li> </ul>			
Transfering										
Transfer log	Add Import	LDAP/AD domain account	Delete							
Point to point tran	ID ±	Full Name	Account	Email		User Groups	Status	Snace Occupation	Create time	Actions
Point to point log		Tun Hume	Account	Lindi		osci didaps	Junus	space occupation	create time	Actions
Share Manager ^	<u> </u>		@ray om (Email)	vision.c			<ul> <li>Offline</li> </ul>	3.35 MB	2020-09-18 14:48:10	Edit   Locked   Delete
Invitation upload	n 1		test			test	Offline	791.76 MB	2020-05-07 15:13:14	Edit   Locked   Delete
Share download										
Email									Totaiz, page172	10/page V
🔜 Users Manager \land										
Users										
Operation records										
User group										

### 2.8.1.7 ユーザーアカウントの削除

[削除]ボタンをクリックすると、ユーザーのアカウントを削除することができます。

S Raysync Enterp	lise   Adm	nin Console									admin V
E	Users										
🗎 Server	( T										
1≣ Transfer ^	Full Na	ame	Account	Email		Status All	<ul> <li>Locked All</li> </ul>	× Search			
Transfering											
Transfer log	Add	I Import L	DAP/AD domain account	Delete							
Point to point tran	100									late design	
Point to point log		ID ¢	Full Name	Account	Email		User Groups	Status	Space Occupation	Create time	Actions
A Share Manager 🔷 🗠		2		i@rayv om (Email)	ision.c			<ul> <li>Offline</li> </ul>	3.35 MB	2020-09-18 14:48:10	Edit   Locked   Delete
Invitation upload	19411							(25.3 ha)			participant in characterization of
Share download		1		test			test	<ul> <li>Online</li> </ul>	791.76 MB	2020-05-07 15:13:14	Edit   Locked   Delete
Email										Total2, page1/2	1 > 10/page ~
≡ Users Manager ^											
Users											
Operation records											

% Tel: +86 18681593969



### 2.8.1.8 ユーザーのオンライン状態の確認

ユーザーのオンライン状態を確認することができます。

🕏 Raysync Enterpr	ise Adr	nin Console								्रिश्चित् admin ~
E E Server	Users									
😫 Tsansfer 💦 -	Full N	lame	Account	Email Status All	- Locked At -	Search				
Current transfers										
Transfer log	Ad	d Import LDAP/AD	domain account							
🖋 Share Manager 🗠							-		-	
Invitation upload		10 1	Full Name	Account	trrai	User Groups	Statue	Space Occupation	Create time	Actions
Share download		1003		test_1		lou	o Offine	0.8	2020-09-08 10:33:09	Edit   Locked   Delete
Email		1001		lou		test	Online	1.15 GB	2020-04-09 16:16:24	Edit   Locked   Delete
za. Users Manager 🗠						lou				
Users		1000	Experience Account	test	test@vaysync.io	test Iou	+ Offine	77.89 MB	2020-04-09 16:12:15	Edit   Locked   Delete
Operation records							<u> </u>		1271	
User group									Total3	page1/3

ステータスをクリックすると、IPアドレスやクライアントの接続番号などのオンライン統計が 表示されます。

	Users									
	Full N	lame	Account	Email Status	All - Locked All -	Search				
	-									
	Ade	i import LDAP/AD	domain account Delate							
	D.L.	ID ¢	Full Name	Account	Email	User Groops	Status	Space Occupation	Create time	Actions
	10	1003		test_1		lou	<ul> <li>Offine</li> </ul>	0 B	2020-09-08 10:33:09	Edit   Locked   Delete
	100	1001		lou		test	• Online	1.15 GB	2020-04-09 16:16:24	Edit   Locked   Delete
n Manager 🗠						lou				
	D.	1000	Experience Account	test	test⊛raysyncio	test	. Offine	77.89 MB	2020-04-09 16:12:15	Edit   Locked   Delete
							1			
							1		Total3.	page1/3 10/pep

IP	Connections
172.16.4.52	1

#### 2.8.1.9 コンフィグ通知メール

[ユーザー設定メール]を選択し、[保存]をクリックすると、ユーザーが設定したメールアドレスから共有リンクメールの通知が送信されます。



Notification Email ⑦ IP login whitelist ⑦	<ul> <li>Admin setting email</li> <li>Enable</li> </ul>						
	Please enter the IP address and separate with '/' if there Such as: 121.211.131.189;10	es that allows to log in a are more than one. 01.234.131.156					
		1					
	Save						

管理コンソールで[ユーザー設定]を選択してから、ユーザー自身のメールアドレスを設定する必 要があります。ログイン後、[メール設定]をクリックします。

🗲 Raysync Enterp	prise			Client Download 🛃 test 🗸 🌾 Transfer List		
A Personal Space	Personal Space			Change Password		
Ø Group Space				Search Log Out Q		
Point to Point	All			loaded 6		
🗇 Share Management	□ Name ↑	Size ↓	Modified ↓	Actions		
	123					
	🗆 🧮 Blender					
	🗌 🧮 file_test					
	□ ■ 新建文件夹44					
	5656	18.49 KB	2020-04-27 15:06:26			
	🗌 🗧 Nit.py	20.00 KB	2019-09-23 12:19:50			
		No More				

メール情報を入力し、[OK]ボタンをクリックします。

U G	After setting email system	will cond potification by this on	aail when	
	share download, invite upl	oad, etc.	ian when	
	* Sender Nickname			
	* Email Provider	Gmail	~	
	* SMTP Email			
	* SMTP Password			
	* SMTP Host	smtp.gmail.com		2020-04-27 1
	* SMTP Port	465		2019-09-23 12
	* Encryption	SSL/TLS	~	
		ОК	Cancel	
			2	

🛞 Website: www.raysync.io 🛛 🗞 Tel: +86 18681593969 🛛 🖂 Email:support@raysync.io



😂 Raysync Enterp	prise	✓ success		Client Download 🛛 🛃 test 🗸 🌾 Transfer List
A Personal Space	Personal Space			
🧶 Group Space				Search file name Q
Point to Point	All			loaded 6
Share Management	□ Name ↑	Size $\downarrow$	Modified ↓	Actions
	123			
	🗌 🧮 Blender			
	🗌 🧮 file_test			
	新建文件夹44			
	5656	18.49 KB	2020-04-27 15:06:26	
	🗌 🧧 测试.py	20.00 KB	2019-09-23 12:19:50	
		No More		

### 2.8.2 ユーザーの容量占有率統計

すべてのユーザーの個人用容量の占有率を統計ができます。管理者管理は、ユーザーがファイル のアップロード、コピー、移動、作成、削除などの操作を行うと、ユーザーの容量使用量をリア ルタイムで計算できます。

😂 Raysync Enterp	S Raysync Enterprise   Admin Console										
⊑ ⊜ Server	Users										
1≣ Transfer ^ Transfering	Full Name	Account	E	Email	Status All ~ Locked All	Search	l				
Transfer log Point to point tran Point to point log	Add Import L	DAP/AD domain account Full Name	Delete Account	Email	User Groups	Status	Space Occupation	Create time	Actions		
	3		test2			<ul> <li>Offline</li> </ul>	0 B	2020-10-16 14:59:22	Edit   Locked   Delete		
Invitation upload Share download	2	test	test			Online	5.33 GB	2020-10-15 16:27:11 Total2, page1/2	Edit   Locked   Delete		
Email Email Users Manager											
Operation records											

ユーザーの容量サイズをクリックすると、容量使用、ファイル数、フォルダ数などの詳細を表示 することができます。

😂 Raysync Enterp	<b>rise</b> Admin Console			C Statistics and Compared Statistics Statistics and Compared Statistics and	C Statistics are in progress, please check back later.				
Ξ	Users								
Server									
t≣ Transfer ^	Full Name	Account	Email	St	atus All ~ Locked All	Search			
Transfering									
Transfer log	Add Import L	DAP/AD domain account							
Point to point tran						Space occupancy details			
Point to point log	ID ‡	Full Name	Account	Email	User Groups	Statu <sub>Space used:0 B/</sub> ion Number of files: 0	Create time	Actions	
🔗 Share Manager \land	□ 3		test2			Off     Number of folders: 0     Refresh	2020-10-16 14:59:22	Edit   Locked   Delete	
Invitation upload	2	test	test			• Online U B	2020-10-15 16:27:11	Edit   Locked   Delete	
Share download							Total2, page1/2	1 > 10/page ~	
Email									
a. Users Manager ∧									
Users									
Operation records									
User group									

[更新]ボタンをクリックして、ユーザー容量の統計を更新することができます。



😂 Raysync Enterpr	rise   Ad	min Console			<ul> <li>Statisti</li> </ul>	<ul> <li>Statistics are in progress, please check back later.</li> </ul>			admin v			
E	Users				ſ							
E Server												
t≣ Transfer ^	Full N	Name	Account	Email		Status All v	Locked All	Ý	Search			
Transfering												
Transfer log	Ad	ld Import	LDAP/AD domain account	Delete								
Point to point tran									Space occupancy details			
Point to point log		ID \$	Full Name	Account	Email	User G	oups	Statu	Space used:0 B/ Number of files: 0	ion	Create time	Actions
🔗 Share Manager 🛛 🔨		3		test2				● Off	Number of folders: 0 Refresh		2020-10-16 14:59:22	Edit   Locked   Delete
Invitation upload		2	test	test				• Onl	ine 0 B		2020-10-15 16:27:11	Edit   Locked   Delete
Share download											Total2, page1/2	1 > 10/page v
Email												
■ Users Manager ^												
Users												
Operation records												

### 2.8.3 ユーザー操作記録

入力して、ユーザー操作記録を表示します。

😂 Raysync Enter	rprise   Control Center				admin
Ξ	Operation records				
Server					
t≣ Transfer ^	Download Download All				
Current transfers	File	Bytes	Time 💠	Download	
Transfer log	optlog.log	1.16 KB	2020-07-22	Download	
Invitation upload	optiog.log.2020-07-17.zip	569 B	2020-07-17	Download	
Share download	optlog.log.2020-07-19.zip	615 B	2020-07-19	Download	
Email	optlog.log.2020-07-20.zip	1.13 KB	2020-07-20	Download	
Users	optiog.log.2020-07-21.zip	777 B	2020-07-21	Download	
Operation records				Page1	-5/Total5 < 1 > 10/page <

ユーザーのログイン、ログアウト、ファイル操作を表示できます。ユーザーのログをダウンロー ドしてローカルで表示できます

😂 Raysync Enterp	prise   Control Center			admin
E	Operation records			
Server				
1≣ Transfer ^	Download Download All			
Towefer log	E File	Bytes	Time \$	Download
Share Manager	☑ optiog.log	1.16 KB	2020-07-22	Download
Invitation upload	optlog.log.2020-07-17.zip	569 B	2020-07-17	Download
Share download	optlog.log.2020-07-19.zip	615 B	2020-07-19	Download
Email	optlog.log.2020-07-20.zip	1.13 KB	2020-07-20	Download
III. Users Manager A	optlog.log.2020-07-21.zlp	777 B	2020-07-21	Download
Operation records				Page1-5/Total5 ( 1 ) 10/page V

### 2.8.4 ユーザーグループ

### 2.8.4.1 ユーザーグループの作成

[グループを追加する]をクリックすると、新しいユーザーグループが追加されます。



😂 Raysync Enter	<b>Dr<i>ise</i>   Control C</b>	enter						admin
Ē	User group							
Server								
l≣ Transfer ^	Add Group	Delete					Search group name	Q. Search
Current transfers	ID	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
Transfer log								
🔗 Share Manager \land	□ 1	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) ; Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	1 > 10/page ~
Share download								
Email								
BL Users Manager A								
Users								
Operation records								
User group								

#### ユーザー情報を入力します

😂 Raysync Enter	o <b>rise</b>   Control G									admin
드 티 Server	User group									
f≣ Transfer ^	Add Group									Q Search
Current transfers	D ID	Group name	Permissions	Group Home Di	Add Group			x ad Limit	Associated users	Actions
Transfer log	0.1	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		*Group name	Required		aad : 0(Mbps) ; Download : 0(Mbps)	View	Edit   Delete
Invitation upload					Group Home Directory	Please fill in the c		d	Page1-1/Total1	1 > 10/page ~
Share download					User group permissions	O Default 💿 Full	O Denied			
Email						List files	Download file			
🚉 Users Manager \land						Create	<ul> <li>Rename</li> <li>Upload file</li> </ul>			
Users						directory				
Operation records					Maximum upload speed		Mt	ps		
User group					download		Mk	ps		
Third-party authe					speed					
Space statistics							No Yes			
A Storage Configura										

[はい]をクリックして、作成します。

### 2.8.4.2 ユーザーグループの編集

😌 Raysync Enterp	o <b>rise</b>   Control Ce	enter						admin
≡ ⊟ Server	User group							
t≣ Transfer ^	Add Group	Delete					Search group name	Q, Search
Current transfers Transfer log	ID	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
🔗 Share Manager \land	0 Ť	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) : Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	1 > 10/page ×
Share download								
Email								
💷 Users Manager 🛛 🔨								
Users								
Operation records								
User group								
Third-party authe								

ユーザーグループ情報の編集



😂 Raysync Enter	D <b>rise</b>   Control C	enter								admin
E	User group									
Server										
1≣ Transfer ^	Add Group	Delete								Q, Search
Current transfers	ID	Group name	Permissions	Group Home Di				ed Limit	Associated users	Actions
Transfer log					Edit Group		×			
🔗 Share Manager \land	0.1	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		*Group name	A project		ad : 0(Mbps) ; Download : 0(Mbps)	View	Edit   Delete
Invitation upload					Group Home Directory	Please fill in the correct path, or the def			Page1-1/Total1	1 10/page v
Share download					User group	O Default   Full O Denied				
Email					permissions	Z List files Z Download file				
BL Users Manager \land						Delete     Create     Create     Delete     Delete     Create     Delete     Deletee     Deleteee     Deleteeeeee     Deleteeeeeeeeeeeeeeeeeeee				
Users						directory				
Operation records					Maximum upload speed	0	Mbps			
User group					download speed	0	Mbps			
Third-party authe					speed					
Space statistics						No	res			
Storana Configura										

### 2.8.4.3 ユーザーグループのユーザーを表示する

[表示]をクリックすると、すべてのユーザーを一覧表示できます

S Raysync Enterp	orise   Control Ce	enter						admin
⊑ ⊜ Server	User group							
1≣ Transfer ^	Add Group	Delete					Search group name	Q Search
Current transfers Transfer log	ID	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
🔗 Share Manager 🔷 🗠	□ f	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) ; Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	> 10/page v
Share download								
Email								
🚉 Users Manager \land								
Users								
Operation records								
User group								

i i	Group H	Associated user of A pro	ject	×	1 Limit	A
ownload file ; Delete ; Rename ; :tory ; Upload file ;		Name/Account	All	✓ Search	id:0(Mbps);Download:0(Mbps)	V
		Associated users	Add users	Delete users		Page
		E Full name	Account			
		angela	Angela			
				Cancel OK		



# 2.8.4.4 ユーザーグループにユーザーを追加する

Group H	Associated user of A proj	ect	x	d Limit
d file ; Delete ; Rename ; Ipload file ;	Name/Account	All	<ul> <li>Search</li> </ul>	ıd : 0(Mbps) ; Download : 0(Mbps)
	Associated users	Add users	Delete users	
	Full name	Account		
	angela	Angela		
			Cancel OK	

Delete											Sea
Group name	Permissions	Add users						x			Asso
A project	List files ; Download file ; Delete ; Re Create directory ; Upload file ;	Search full na	ime, account	Search		Selected(1)			(lbps) ; Download :	0(Mbps)	View
		Full name	Account	all	<b>→</b>	Full name	Account test	Clear			Page1-1
							Can	cel OK			



# 2.8.4.5 ユーザーグループのユーザーを削除する

					[
ssions	Group H	Associated user of A pro	ject X	d Limit	A
es ; Download file ; Delete ; Rename ; e directory ; Upload file ;		Name/Account	All × Search	id: 0(Mbps): Download: 0(Mbps)	1
		Associated users	Add users Delete users		Pag
		Full name	Account		
		angela	Angela		
		🔽 test	test		
			Cancel OK		

### 2.8.4.6 ユーザーグループの削除

😂 Raysync Enterp	o <b>rise</b>   Control C	enter						admin
E	User group							
Server								
t≣ Transfer ^	Add Group	Delete					Search group name	Q Search
Current transfers	D	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
Transfer log								P
& Share Manager 🔷 🗠	1	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) : Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	1 > 10/page ->
Share download								
Email								
🚉 Users Manager 🛛 🗠								
Users								
Operation records								
User group								



#### 2.8.4.7 検索

😂 Raysync Enterp	<b>orise</b>   Control Co	enter						admin
⊑ ≣ Server	User group							
t≣ Transfer ^	Add Group	Delete					Search group name	Q Search
Current transfers	D ID	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
e Share Manager ^	01	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) : Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	> 10/page ×
Share download Email								
💵 Users Manager 🔷 🗠								
Users								
Operation records User group								

### 2.8.4.8 ユーザーグループ容量の占有率統計

ユーザーグループ容量の占有率を統計することができます。管理者管理は、ユーザーがグループ 内のファイルのアップロード、コピー、移動、作成、削除などの操作を行うと、グループの使用 量をリアルタイムでカウントできます。

😂 Raysync Enterp	o <b>rise</b>   Control Ce	enter						admin
드 B Server	User group							
till Transfer 🔷 ^	Add Group	Delete					Search group name	Q Search
Current transfers Transfer log	DID	Group name	Permissions	Group Home Directory	Space occupation	Speed Limit	Associated users	Actions
& Share Manager ^	0.1	A project	List files ; Download file ; Delete ; Rename ; Create directory ; Upload file ;		0 B	Upload : 0(Mbps) : Download : 0(Mbps)	View	Edit   Delete
Invitation upload							Page1-1/Total1	> 10/page >
Share download Email								
IIIL Users Manager \land								
Users								
Operation records User group Third-party authe								

容量占有率をクリックして、使用容量のサイズ、ファイル数、フォルダ数などの詳細を確認して ください。

😂 Raysync Enter	p <b>rise</b>   Control (	enter						admin
⊑ Bi Server	User group							
t≣ Transfer ^	Add Group	Delete			Space occupancy details		Search group name	Q. Search
Current transfers	D	Group name	Permissions	Group Home Directory	Number of files: 0 Number of folders: 1 pn	Speed Limit	Associated users	Actions
Transfer log	01	A project	List files ; Download file ; Delete ; Rename ; Create directory : Unload file :		0 B	Upload : 0(Mbps) ; Download : 0(Mbps)	View	Edit   Delete
Invitation upload			ereare anectory, apread me,				Page1-1/Total1	1 > 10/page v
Share download								
Email								
Users								
Operation records								
User group								

# 2.8.5 第三者認証

#### 2.8.5.1 LDAP/AD 設定



います。

ドメインサーバーアドレス、ドメイン名、ドメイン管理者アカウント、ドメイン管理者パスワー ドを入力し、[テスト]をクリックします。テストパスは、情報が正しく記入されていることを示 しています。

😂 Raysync Enterp	Se Raysync Enterprise   Admin Console									
E	Third-party auth									
Server										
t≣ Transfer ^	When you select LDAP/AD domain or mailbox	x authentication to log in, the account created manually in Raysync Management also supports login.								
Transfering	When you select System or external HTTP aut	hentication to log in, the account created manually in Raysync Management Center will not be able to log	g in.							
Transfer log	* Authentication Type 🕓 None 💿 LDAP/AD	) domain 📀 Email 💿 Unix system 💿 External http								
Point to point tran	After selecting this authent	tication, you can configure the default permissions of domain accounts first, and then import domain accounts in users								
Point to point log	* Server Address	(E.g. Idap://192.168.1.131:789/)								
🔗 Share Manager 🛛 🗠	* Domain Name	(E.g. dc=test,dc=com)								
Invitation upload	* Admin Username									
Share download	* Admin Password									
Email	Test	Save								
≡ Users Manager ∧										
Users										
Operation records										

[保存]をクリックして、ドメインキープ認証を行います

#### [アカウントのデフォルトの権限を設定する]をクリックします

SRaysync Enterprise Admin Console										
E	Third-party auth									
E Server										
t≣ Transfer ^	When you select LDAP/AD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.									
Transfering	When you select System or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.									
Transfer log	* Authentication Type 📀 None 💿 LDAP/AD domain 💿 Email 💿 Unix system 💿 External http									
Point to point tran	After selecting this authentication, you can configure the default permissions of domain accounts first, and then import domain accounts in users									
Point to point log	* Server Address (E.g. Idap://192.168.1.131:789/)									
🔗 Share Manager 🛛 🗠	* Domain Name (E.g. dc=test,dc=com)									
Invitation upload	* Admin Username									
Share download	* Admin Password									
Email										
🚉 Users Manager \land	lest 24ve									
Users										
Operation records										
User group										
Third-party auth										

[Auth A/C 設定]インターフェースに入り、LDAP/AD アカウントの権限を設定します。 ヒント:ログインしていないアカウントにのみ有効です。 ログイン中のアカウントは、アカウ ント情報リストから権限を変更することができます。



=	Auth A/C setting										
E Transfar											
Transfering	LDAP / ad domain & r System & external HT	LDAP2 and domain & mailtox submetications this page configurations is only valid for the merging logged in accounts in these two submetications methods will be account information is at System & external in The submetications exclusion logged in accounts in these two submetications methods will be account information is at System & external in The submetications exclusion logged in accounts in these two submetications methods will be account information is at System & external in The submetications exclusion logged in accounts in the present account information, so if you need to charge account configuration is defined by the submetication methods will be general account information, so if you need to charge account configuration exclusion site account information is at system account information in the system account information in the system account information is system account information account information account information account information, so if you need to charge account configuration account information is system account information account information account information account information is system account information accou									
Transfer log	A second to the selection										
Point to point trap	mode	LDAP/AD domain									
Point to point trait	User Groups	Add									
Point to point log	Permissions	🔿 Default 💿 Selec	t all ု Reverse all								
Share Manager		List files	Upload file	Download file	Create directory						
Invitation upload		Rename	Delete	💟 Сору	Move						
Share download		Share	Invite								
Email											
Users Manager ^	Max Upload Speed ③	0		Mbps							
Users	Max Download Speed (	0		Mbps							
Operation records	Sync 💿	Inable									
User group	File Format Whitelist ⑦	Enable									
Third-party auth											
Auth A/C setting		suffix name that allows Please use multiple form	the user to transfer the file. Nats: such as: bit: exe:								
Space statistics											
Send notification				2							
Storage config	Notification Email (?)	<ul> <li>Admin setting emi</li> </ul>	ail 🔿 User setting ema	ail							
Advanced Setting ~	IP login whitelist ③	Enable	na anna ann an Airtean an Airtean an Airtean an Airtean an Airtean an Airtean Airtean Airtean Airtean Airtean A								
Personalization		Please enter the IP addr and separate with 1 if th Such as 121,211,131,18	esses that allows to log in sere are more than one 9:101.234.131.156								
		S	iave .	i.							

#### 2.8.5.2 メール認証

SMTP ホスト、SMTP ポート、使用した暗号化方式、テストアカウント、パスワードを入力し、[テスト]をクリックします。テストパスは、情報が正しく記入されていることを示しています。 保存]をクリックすると、有効になります。

😂 Raysync Enterpr	ise   Admin Console						
Ē	Third-party auth						
📑 Server							
1≣ Transfer ^	When you select LD	AP/AD domain or mailbox aut	hentication to log i	n, the account created	manually in Raysync Man	agement also supports log	gin.
Transfering	When you select Sys	stem or external HTTP authent	ication to log in, th	e account created man	ually in Raysync Manager	nent Center will not be ab	le to log in.
Transfer log	* Authentication Type	e 🔿 None 🔿 LDAP/AD do	main 💿 Email 🔾	) Unix system 🔿 Ext	ternal http		
Point to point tran		Support configure the default p	ermissions of the acco	u <mark>nt.</mark> After account login, yo	ou can change the permission	s of a single account.	
	* Email Provider	Gmail	~				
Point to point log							
🔗 Share Manager 🛛 🗠	* SMIP Host	smtp.gmail.com					
Invitation upload	* SMTP Port	465					
Share download	* Encryption	SSL/TLS	~				
Email							
- Horr Managar	* Test Account						
	* Test Password						
Users							
Operation records		Test	Save				
User group							

[アカウントのデフォルトの権限を設定する]をクリックします



😂 Raysync Enterpri	iSe   Admin Console	
E.	Third-party auth	
E Server		
t≣ Transfer ^	When you select LDA	PAD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.
Transfering	When you select Syste	em or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.
Transfer log	* Authentication Type	O None O LDAP/AD domain 💿 Email O Unix system O External http
Point to point tran		Support configure the default permissions of the account. After account login, you can change the permissions of a single account.
Point to point log	* Email Provider	Gmail 🗸
🔗 Share Manager \land	* SMTP Host	smtp.gmail.com
Invitation upload	* SMTP Port	465
Share download	* Encryption	SSL/TLS 🗸
Email	* Test Account	
🚉 Users Manager 🛛 🔺	* Test Descuord	
Users	rest rassword	
Operation records		Test Save
User group		
Third-party auth		

[Auth A/C 設定]インターフェースに入り、メールアドレスアカウントの権限を設定します。 ヒント:ログインしていないメールアドレスにのみ有効です。 ログイン中のアカウントは、ア カウント情報リストから権限を変更することができます。

1 Transfer ^	LDAP / ad domain & m System & external HTTI	allbox authentication: t P authentication: accou	his page configuration nts logged in through t	is only valid for the net these two authenticatio	wly logged in accounts in th on methods will not generate	ese two authentication methods. The con e account list in account information, so i	figuration of the logged in acc f you need to change account	count can be modified thro configuration, edit this pag	ugh the account information list e	
Transfering										
Transfer log	Current authentication	Email								
Point to point tran	User Groups	Add								
Point to point log	Parmissions	Default     Select	all Reverse all							
🔗 Share Manager 🗠 🗠	10111031010	o bolant o bolant								
Invitation upload		List files	Upload file	Download file	Create directory					
Share download		Share	Invite	ору	MOVE					
Email										
⊒L Users Manager A	Max Upload Speed ③	0		Mbps						
Users	Max Download Speed @	0		Mbps						
Operation records	Sync ②	Fnable								
User group	Ella Format Whiteliat	Enable								
Third-party auth	The format writtenst 🕤	I criative								
Auth A/C setting			he user to transfer the file. ats; such as: bit; exe;							
Space statistics										
Send notification			1	2						
🖨 Storage config	Notification Email (?)	Admin setting ema	il 🕜 User setting ema	ail						
Advanced Setting ~	IP login whitelist ③	Enable								
⊕ Personalization		Please enter the IP addre and separate with 10 if th Such as: 121,211,131,185	esses that allows to log in ere are more than one. (101234.131.156	e						
		S	ave							

#### 2.8.5.3 Unix システム認証

Linux システムの root アクセス許可または sudo アクセス許可で起動した raysync サービスは、 Linux システムのユーザー認証の設定に対応しています。

Unix システム認証を選択し、[保存]をクリックします。設定が成功すれば、linux システムの ユーザーアカウントとパスワードを使って、直接 raysync スピードサービスにログインすること ができます。

ヒント:通常の linux システムユーザーが起動した raysync サービスであれば、この設定を実行 する権限はありません。

🛞 Website: www.raysync.io 🛛 💊 Tel: +86 18681593969 🛛 🖂 Email:support@raysync.io



🗲 Raysync Enterp	rise   Admin Console
E	Third-party auth
E Server	
1≣ Transfer ^	When you select LDAP/AD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.
Transfering	When you select System or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.
Transfer log	* Authentication Type 💿 None 💿 LDAP/AD domain 💿 Email 💿 Unix system 💿 External http
Point to point tran	Support configure the default permissions of the account.
Point to point log	Save
🔗 Share Manager 🛛 🗠	
Invitation upload	
Share download	
Email	
🛋 Users Manager 🛛 🗠	
Users	
Operation records	
User group	

#### [アカウントのデフォルトの権限を設定する]をクリックします

E	Third-party auth
Server	
t≣ Transfer ^	When you select LDAP/AD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.
Transfering	When you select System or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.
Transfer log	* Authentication Type O None O LDAP/AD domain O Email 💿 Unix system O External http
Point to point tran	Support configure the default permissions of the account.
Point to point log	Save
🔗 Share Manager 🔗	
Invitation upload	
Share download	
Emall	
🖦 Users Manager 🗠	1

#### [Auth A/C 設定]インターフェースに入り、Unix アカウントの権限を設定します。

Auth A/C	C setting				
nsfer ^	P / ad domain & ma	ellbox authentication	n: this page configuration	is only valid for the new	why longed in accounts in th
fering Infor	mation list	authoritestion and	munte logged in through	there have a threatly allo	s methods will not opport
ransfer log	DH & CACING DITE	autication, aco	mese two autoenticatio	in methods will not generate	
oint to point tran Curren	nt authentication	Unix system			
nt to point log Permis	ssions	🔿 Default 💿 Selr	iect all ု 🔿 Reverse all		
re Manager 🗠				-	_
ritation unload		Rename	Upload file Delete	Conv	Create directory     Move
hara download		Share	Invite		
Email:					
Max U	Jpload Speed ()	0		Mhps	
Max D	Jownload Speed (2)	0			
ers Sugar (	<i>a</i> . 1	-			
eration records Sync C	1. 	Enable			
group File Fo	urmat Whitelist ③	Enable			
ird-party auth			55 characters/Flease enter the values to transfer the file.		
with A/C setting			omati, such all tat, exe		
Space statistics				4	
Send notification					
Storage config	1				
Advanced Setting +			Save	4	



### 2.8.5.4 外部 http 認証

認証するため、外部 http サービスを利用できます。

[ユーザー管理-第三者認証]をクリックし、[外部 http]を選択します。そして、サービス URL を入力して、[保存]をクリックします。

設定が成功すれば、設定した外部 http サービスシステムのユーザーアカウントとパスワードから直接ログインすることができます。

ų	Raysync Enterpr	iSe   Admin Console	
Ē	2 2 2	Third-party auth	
E	Server		
1≣	Transfer ^	When you select LDAP/AD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.	
	Transfering	When you select System or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.	
	Transfer log	* Authentication Type 💿 None 💿 LDAP/AD domain 💿 Email 💿 Unix system 💿 External http	
	Point to point tran	Support configure the default permissions of the account.	
	Point to point log	* Service URL http://127.0.0.1:8090/raysync/api/third (E.g. http://127.0.0.1:8090/raysync/api/thirdparth/auth/)	
Ð	Share Manager 🛛 🔨	Save	
	Invitation upload		
	Share download		
	Email		
=1	. Users Manager \land		
	Users		
	Operation records		
	User group		
	Third-party auth		

#### [アカウントのデフォルトの権限を設定する]をクリックします

😂 Raysync Enterpi	r <i>İSE</i> Admin Console
E	Third-party auth
E Server	
t≣ Transfer ^	When you select LDAP/AD domain or mailbox authentication to log in, the account created manually in Raysync Management also supports login.
Transfering	When you select System or external HTTP authentication to log in, the account created manually in Raysync Management Center will not be able to log in.
Transfer log	*Authentication Type O None O LDAP/AD domain O Email O Unix system O External http
Point to point tran	* Service URL http://127.0.0.1:8090/ravsync/api/third (E.g. http://127.0.0.1:8090/ravsync/api/thirdparth/auth/)
Point to point log	
& Share Manager \land	Save
Invitation upload	
Share download	
Email	
sers Manager ∧	

[Auth A/C 設定]インターフェースに入り、外部 http アカウントの権限を設定します。



⊑ ⊜ Server	Auth A/C setting										
f≣ Transfer ^	LDAP / ad domain & m	LDAP / ad domain & mailbox authentication: this page configuration is only valid for the newly logged in accounts in these two authentication methods. The configuration of the logged in account can be modified through the account in these two authentication methods.									
Transfering	Information list System & external HTTP authentication: accounts logged in through these two authentication methods will not generate account list in account information, so if you need to change account configuration, edit this page										
Transfer log Point to point tran	Current authentication mode	Current authentication External http									
Point to point log	Permissions O Default   Reverse all										
🔗 Share Manager 🛛 🔨		List files	Upload file	Download file	Create directory						
Invitation upload		Rename	🗹 Delete	🗹 Сору	Move Move						
Share download		Share	🗹 Invite								
Email											
≡ Users Manager ^	Max Upload Speed ⊘	0		Mbps							
Users	Max Download Speed @	0		Mbps							
Operation records	Sync 💿	Enable									
User group	File Format Whitelist ⊘	Enable									
Third-party auth			5 characters)Please enter the								
Auth A/C setting			mats; such as: txt; exe:								
Space statistics											
Send notification			~ ^								
Storage config		_									
Advanced Setting      -			Save								

# 2.8.6 容量統計

更生容量の統計期間に対応しています。

1時間に設定した場合、システムは1時間ごとに、ユーザーとユーザーグループが占有する容量 を自動的に計算します。

1	Raysync Enterp	orise   Control Center
E		Space statistics
	Server	
1≣	Transfer ^	Statistical period setting 1 hour(s)
	Current transfers	Save
	Transfer log	
65	Share Manager ^	
	Invitation upload	
	Share download	
	Email	
31	Users Manager 🛛 ^	
	Users	
	Operation records	
	User group	
	Third-party authe	
	Space statistics	
0	Storage Configura	
	Advanced Setting ~	
Û	Personalization	



# 2.8.7 Auth A/C 設定

LDAP/AD ドメイン&メール認証は、新規にログインしたアカウントのデフォルト権限を設定する ことができます。ログインしたアカウントは、アカウント情報を編集することができます。

Ark Ac Setting   Transfer	😂 Raysync Enterpr	SØ   Admin Console
Server S	E	Auth A/C setting
I Torder   Tarder   th <th>E Server</th> <th></th>	E Server	
Taraforing       Splete & defend (ITP althetication: actional though these has addividual on reduced and net prevents account long prevents account configuration, red this page         Taraforing       Guing to addividual though these has addividual on reduced and net prevents account long prevents account configuration, red this page         Painter book       Guing to addividual though these has addividual on reduced and net prevents account long prevents account configuration, red this page         Painter book       Guing to addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though these has addividual though though these has addividual though though these has addividual though thou	t≣ Transfer ^	LDAP / ad domain & mailbox authentication: this page configuration is only valid for the newly logged in accounts in these two authentication methods. The configuration of the logged in account can be modified through the account information list
Tander log Chromet and heading in all   Point to point too   Point too <th>Transfering</th> <th>System &amp; external HTTP authentication: accounts logged in through these two authentication methods will not generate account is in account information, so it you need to change account configuration, edit this page</th>	Transfering	System & external HTTP authentication: accounts logged in through these two authentication methods will not generate account is in account information, so it you need to change account configuration, edit this page
Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   Point to point rom   P	Transfer log	Courter authentication Email
Not down   Not down   Not down   Share Amager   Intradiant upbadd   Share I intradiant upbadd   Shar	Point to point tran	Here Groupe Add
Share Manager   Invitation upload   Share download   Email   Is Users Manager   Max Upload Speed ()   Operation records   Users   Operation records   Sync ()   E fable   File Format Whitelist ()   E fable   Is Storge config   Advanced Setting   Personalization   Nettification tenal () Index tenal tenade to to the setting tenal () Versonalization	Point to point log	
Invitation upload   Share download   Enail   Share download   Enail   Share download   Enail   Share download   Coperation records   Uters group   Tuid-party auth   Auth Ark setting   Space statistics   Space s		Permissions Default Call Reverse all
Share download   inal    inal   inal <tr< th=""><th>Invitation upload</th><th>C List files Dupload file C Download file C Create directory</th></tr<>	Invitation upload	C List files Dupload file C Download file C Create directory
Ensile       Initial       Initial         Subset       Max Upload Speed ()       Initial         Users       Max Domibad Speed ()       May         Operation records       Sync ()       Inable         Titrd-party auth       File Format Whitelit ()       Inable         Space statistics       Send notification       Inable         Space statistics       Inable       Inable         Space statistics       Send notification       Inable         Personalization       Inable       Inable         Pressonalization       Inable       Inable	Share download	Bename Delete D Copy D Move
a. Uters Manager   Users   Operation records   User group   Third-party auth   Auth ACC setting   Space statistics   Send nutrification   Send nutrification   Advanced Setting   Personalization     Auth ACC setting   Operation records   Space statistics   Send nutrification   Personalization     Notification Email   Operation records   Personalization     Auth ACC setting     Operation records   Send nutrification     Personalization     Notification Email   Operation records   Send nutrification     Personalization     Personalization     Notification Email     Operation records   Send nutrification     Personalization     Personalizatio	Email	Share Invite
Max Upbad Sped () 0   Max Upbad Sped () 0   Max Upbad Sped () 0   Max Upbad Sped () 0   Max Downled Sped () 0   Max Downled Sped () 0   Spric () 0   File Format Whitelist () Enable   File Format Whitelist () Enable   Spric config 0   Advanced Setting - 0   Advanced Setting - 0   Personalization 0   Personalization 0	s Users Manager A	
Mac Download Spreet () ()     Macy       Operation records     Sync ()     Inside       Trind-party auth     File format Whitelist ()     Inside       Auth AUC setting     Sync ()     Inside       Sprace statistics     Setting config     Advanced Setting       Stongs config     Advanced Setting     Image Setting condition       Personalization     Personalization     Image Setting condition	liters	Max Upload Speed () 0 Mitigan
Sync 0       Imable         User group       File Format Whitelit 0       Imable         Third-party auth       File Format Whitelit 0       Imable         Auth A/C setting       Imable       Imable         Space statistics       Please there the super threader the file         Storage config       Admin setting email       User setting email         Advanced Setting *       Please where the Please there the Please in the User setting email         Personalization       Please where the Please there the Please in the User setting email         Storage config       Advanced Setting *         Personalization       Please where the Please there the Please in the User setting email         Storage config       Storage config         Personalization       Please where the Please into the User setting email         Storage config       Storage config         Storage config       Storage config         Personalization       Please where the Please into the User setting email         User of the User of	Osers	Max Download Speed 💿 0 Milear
User group       File Format Whiteliat ()       Enable:         Tind - Jack and Costing       Early in its the 255 choses of back as a to though it to file.         Space statistics       Please use multiple formats such as to though it to file.         Storage config       Admin setting email       User setting email         Advanced Setting -       Personalization       Enable:         Personalization       Enable:       Enable:         Storage config       Admin setting email       User setting email         Advanced Setting -       Personalization       Enable:         Storage config       Storage config       Storage config         Advanced Setting -       Personalization       Enable:         Storage config       Storage config       Storage config         O Personalization       Admin setting email       User setting email         IP login whiteliat ()       Enable:       Storage config         Storage config       Storage config       Storage config         O Personalization       Personalization       Storage config         Biogin whiteliat ()       Enable:       Storage config         Storage config       Storage config       Storage config         O Personalization       Storage config       Storage config	Operation records	Sync 🕥 🗧 Enable
Tind Carly aufh     Ianghi Is tab the 25 document for faces and the face       Auh AC settion     Faces and the faces to tab document for faces and the face       Space statistics     Please supervise faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab the set tab document for faces and tab tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for faces and tab document for	User group	File Format Whitelist 🗇 🗌 Enable
Auth AC setting     Lotte name that alloss that all to the all alloss that alloss that all to the alloss that all to the alloss that all to the alloss that alll	Third-party auth	Carryph is less than 255 characters(Please and/or the
Space statistics       Image: Config and Config         Storage config       Advanced Setting -         Advanced Setting -       Image: Config and Config	Auth A/C setting	Sufficience that address date to besider the time. Plaque que to high the formits que to the size.
Send natification     Image: Config       Advanced Setting     Image: Config       Personalization     Image: Config       Personalization     Image: Config       Image: Config     Image: Config       Image: Config <th>Space statistics</th> <th></th>	Space statistics	
Storage config       Notification Email ① ② Advanced Setting • mail ① User setting email ② User setting email ③ User setting email ③ Plasse enter the IP addresses that allows to log in and securate with ⑦ thema as mine that one fact	Send notification	
Advanced Setting      IP login whitelist     □     Plasse enter the IP addresses that allows to log in     and separate with. If these as more than one.     Sorther: 12121131105101234131136	😂 Storage config	Notification Email 💿 🙆 Admin setting email
Personalization Plasse enter the IP addresses that allows to log in and separate with, if these as an most Such as 12(2)(13)(10)(12)(24)(3)(36)	Advanced Setting ~	IP login whitelist 🕖 🛛 Enable
	♀ Personalization	Program entrop (etc.)         Bit Starts etc.)         Bit Starts etc.)           Program entrop (etc.)         Program etc.)         Bit Starts etc.)           Program etc.)         Program etc.)         Bit Starts etc.)

システム&外部 http 認証では、全アカウント権限を設定できます。

認証を変更した後に[保存]をクリックすると、設定が保存され、認証ユーザー権限が有効になり ます。

🕏 Raysync Enterpr	Se   Admin Console						admin 🗸
E	Auth A/C setting						
E Server							
t≣ Transfer ^	LDAP / ad domain & r System & external HT	nailbox authentication TP authentication: acc	this page configuration ounts logged in through	is only valid for the net these two authentication	vly logged in accounts in th n methods will not generate	ese two authentication methods. The configuration of the logged in account can be modified through the account information list e account list in account information, so if you need to change account configuration, edit this page	
Transfering							
Transfer log	Current authentication mode	Email					
Point to point tran	User Groups	Add					
Point to point log	Permissions	🔾 Default 💿 Sele	ect all 🔿 Reverse all				
📌 Share Manager 🗠		-					
Invitation upload		Rename	Opioad file     Delete	Copy	Move		
Share download		Share	Invite				
Email							
💷 Users Manager 🗠	Max Upload Speed ③	0		Mbps			
Users	Max Download Speed (	0		Mbps			
Operation records	Sync ③	Enable					
User group	File Format Whitelist (7)	Enable					
Third-party auth							
Auth A/C setting			is the user to transfer the file. immata; such as: tot; exe:				
Space statistics							
Send notification				ŝ			
Storage config	Notification Email ③	<ul> <li>Admin setting er</li> </ul>	mail 🗍 User setting em	ail			
Advanced Setting ~	IP login whitelist ③	Enable					
Personalization		Please enter the IP ad	dresses that allows to log in				
		Such as: 121.211.131.					
				a			
			Save .				

🌭 Tel: +86 18681593969



### 2.8.8 通知を送信

#### 2.8.8.1 通知の追加

[知を追加する]をクリックします。

ヒント:この機能を利用する前に、管理者がメールアドレスの設定を行う必要があります。 PRaysync Enterprise Admin Console

⊑ ≣ Server	Send notification							
t≣ Transfer ^	Add notification						Please enter subject Q	Search
Transfering Transfer log	ID	Subject	Content	Receiving accounts	Notification option	Create time	Actions	
Point to point tran								
Point to point log				No Data				
Invitation upload								
Share download								
Email ≡ Users Manager ∧								
Users								
Operation records								
Third-party auth								
Auth A/C setting								
Space statistics Send notification								

サブジェクトと内容を入力します。

😂 Raysync Enterp	rise   Admin Consol	e											admin 🗸
E	Send notification												
Server													
t≣ Transfer ^	Add notificatio	on -											Q. Search
Transfering	10	6.12.4	<b>C</b>										A
Transfer log	U	Subject	Com	Add notification	1						×	eate time	Actions
Point to point tran				Subject									
Point to point log				Content									
🔗 Share Manager 🔷 🗠			_									_	
Invitation upload				Rosolvána							11		
Share download				accounts	Account	Email	全选		Account	Email	Clear		
Email					ravvision com	)							
■ Users Manager ^					test								
Users								$\rightarrow$					
Operation records													
User group													
Third-party auth													
Auth A/C setting				Notification op	ion	Email							
Space statistics													
Send notification										Canc	el OK		

通知を受信するユーザーアカウントを選択します。複数のユーザーアカウントを同時に選択する こともできます。



🗧 Raysync Enterp	rise Admin Cons	ole											admin 🗸
⊆ ⊟ Server	Send notification	1											
t≣ Transfer ∧	Add notifica	tion											Q. Search
Transfering								_			_		1000
Transfer log	ID	Subject	Cont	Add notifica	tion						x	eate time	Actions
Point to point tran				Subject									
Point to point log				Content									
P Share Manager 🔷													
Invitation upload													
Share download				accounts	Account	Email	全选		Account	Email	Clear		
Email									Constitution com	5	0		
🛋 Users Manager 🗠									test		0		
Users								$\rightarrow$					
Operation records													
User group													
Third-party auth													
Auth A/C setting				Notification	option	e Email							
Space statistics													
Send notification										Cano	iel OK		
Storage config													
Card and a state of the state of the													

通知の方法を選択します:ウェブページ、メールなど。

ヒント:メッセージの通知方法をメールにする場合、通知メールを受信するためのユーザーアカ ウント情報を入力する必要があります。

😂 Raysync Enterpr	r <b>ise</b>   Admin Conso	le												admin $\vee$
⊑ ⊟ Server	Send notification													
f≣ Transfer ^	Add notificati	on											Q	Search
Transfering Transfer log	ID	Subject	Cont	Add notificatio	n						×	eate time	Actions	
Point to point tran				Subject										
Point to point log				Content										
🔗 Share Manager 🛛 🗠												_		
Invitation upload				Pacalular							11			
Share download				accounts	Account	Email	全选		Account	Email	Clear			
Email									heguocheng@ ravvision.com		٥			
🚉 Users Manager \land									test		Θ			
Users								$\rightarrow$						
Operation records														
User group														
Third-party auth							1							
Auth A/C setting				Notification op	tion Website	Email								
Space statistics				-										
Send notification										Cancel	OK			
Storage config														
Advanced Setting      ^														

[OK]をクリックします。



🗧 Raysync Enterpr	İSƏ 🛛 Admin Console												admin ~	
E	Send notification													
🗐 Server														
t≣ Transfer ^	Add notification												Q Search	
Transfering	ID	Subject	Cont				_	_				eate time	Actions	
Transfer log		Jubject	Com	Add nouncation							*	cate time	Actions	
Point to point tran				Subject										
Point to point log				Content										
🔗 Share Manager 🛛 🗠			_									_		
Invitation upload				Pacalulan							h			
Share download				accounts	Account	Email	全选		Account	Email	Clear			
Email									heguocheng@ ravvision.com		0			
🚉 Users Manager 🛛 🗠									test		0			
Users								$\rightarrow$						
Operation records														
User group														
Third-party auth														
Auth A/C setting				Notification on	ion Mebrite	Email								
Space statistics				Nouncation op	ion vebsite	Lindi								
Send notification										Cancel	ОК			
😝 Storage config														
Advanced Setting      ^														

システムは送信成功と表示します。

😂 Raysync Enterp	rise A	dmin Console		The notification has been set of the set	en sent successfully				admin ~
≘ ⊜ Server	Send	notification							
t≣ Transfer ^		Add notification						Please enter subject	Q Search
Transfering Transfer log	ID	Subject	Content			Receiving accounts	Notification option	Create time	Actions
Point to point tran	1	test	test		~	2	Website	2020-10-16 16:58:04	Delete
Point to point log								Total1, page1/1 🔄 🚺	> 10/page ~
Invitation upload									
Share download									
Email									
Users									
Operation records									
User group Third-party auth									
Auth A/C setting									
Space statistics									
Send notification									

### 2.8.8.2 検索通知

右上では、通知を検索することができます。検索ボックスはファジークエリに対応しています。

S Ruysyne Enterpr	Joe Admin	console							dunin -
⊑ ⊜ Server	Send notific	cation							
t≣ Transfer ^	Add no	otification						test	Q Search
Transfering Transfer log	ID	Subject	Content			Receiving accounts	Notification option	Create time	Actions
Point to point tran Point to point log	1	test	test		~	2	Website	2020-10-16 16:58:04	Delete
& Share Manager ^								Total1, page1/1 🔄 🚹	> 10/page >
Invitation upload									



### 2.8.8.3 通知の削除

迪州を選択し、  削尿  をノノソノしよ	通知を選択し、	[削除]をク	リックします
----------------------	---------	--------	--------

😌 Raysync Enterpr	<i>'ISE</i> Admin	Console							admin ~
⊑ ■ Server	Send notific	ation							
f≣ Transfer ^	Add no	tification						test	Q Search
Transfer log	ID	Subject	Content			Receiving accounts	Notification option	Create time	Actions
Point to point tran Point to point log	11	test	test		~	2	Website	2020-10-16 16:58:04	Delete
Share Manager ^								Total1, page1/1	1 > 10/page v
Invitation upload								/	
Email									

ページに削除ボックスがの確認が表示されますので、[削除]をクリックしてください。

⊑ ≣ Server	Sen	d notificati	on								
t≣ Transfer ∧		Add notifi	cation		Delete notification     Are you sure to delete	n e?				test	Q. Search
Transfering Transfer log			Subject	Content		Cancel	Delete	Receiving accounts	Notification option	Create time	Actions
Point to point tran Point to point log			test	test					Website	2020-10-16 17:08:24	Delete
Share Manager ^ Invitation upload	-									Total1, page1/1	1 10/page ~
Share download Email											
■ Users Manager ∧ Users											

削除しました。

😂 Raysync Enterp	<i>rise</i>   Admin Con	sole		🥝 Delete success			admin ~
E	Send notificatio	p					
Server							
t≣ Transfer ^	Add notific	ation					test Q. Search
Transfering			- 100	-			
Transfer log	ID	Subject	Content	Receiving accounts	Notification option	Create time	Actions
Point to point tran							
Point to point log				No Data			
🔗 Share Manager \land							
Invitation upload							
Share download							
Email							
■ Users Manager ^							

### 2.8.8.4 通知の受信するアカウントを表示

数字をクリックします。



😂 Raysync Enterp	<i>rise</i>   Admin	I Console								admin 🗸
드 目 Server	Send notifi	cation								
t≣ Transfer ^	Add n	otification							Please enter subject	Q Search
Transfering Transfer log	ID	Subject	Content				Receiving accounts	Notification option	Create time	Actions
Point to point tran	3	tsetset	setsetset		~		2	Website Email	2020-10-16 17:12:48	Delete
Share Manager ^						/			Total1, page1/1	1 > 10/page ~
Invitation upload						/				
Share download										
Email										
Users										

通知を受けたユーザーのアカウント情報とメール情報が表示されます。

🗧 Raysync Enterpi	Raysync Enterprise   Admin Console								
드 目 Server	Send notific	id notification							
t≣ Transfer ^	Add no	tification							Q Search
Transfering Transfer log	ID	Subject	Content		Notification accounts	×	Notification option	Create time	Actions
Point to point tran	3	tsetset	setsetset		Account	Email	Website Email	2020-10-16 17:12:48	Delete
Point to point log					test			Total1, page1/1	10/page~
🔗 Share Manager 🛛 🗠									
Invitation upload					@rayvision.com				
Share download									
Email						Shutdown			
■ Users Manager ^									
Users									
Operation records									

### 2.9 ストレージ設定

### 2.9.1 ローカルストレージ

ローカルストレージのパスは、ユーザーのホームディレクトリのパスを指定に使用されます。 例えば、「test1」という名前のユーザーを作成すると、 raysync サーバーは指定されたストレ ージパスに「test1」という名前のフォルダを自動的に作成します。ユーザーがアップロードや ダウンロードしたファイルやフォルダは、このフォルダに入ります。

😂 Raysync Enterpi	r <b>ise</b> Admin Console	
E	Storage config	
E Server		
1≣ Transfer ^	* Storage Provider	● Local storage
Transfering	* Default Path	FARavevnrawindrow/3.4.4.8/RavSvnra3.4.4.8,7011.uvin32/Raver
Transfer log		ו איז איז איז איז איז איז איז איז איז איז
Point to point tran		Save
Point to point log		
🔗 Share Manager \land		
Invitation upload		
Share download		
Email		
🛋 Users Manager \land		

Website: www.raysync.io

% Tel: +86 18681593969

Email:support@raysync.io



# 2.9.2 Alibaba クラウド OSS

OSS ストレージの設定を入力し、[テスト]をクリックします。 通過したら、保存してください。次回起動すると有効になります。

😂 Raysync Enterp	orise Admin Console	
Ē	Storage config	
📑 Server		
t≣ Transfer ^	* Storage Provider	○ Local storage 💿 Alibaba cloud OSS ○ Amazon S3 ○ S3 interface compatible storage ○ Azure Blob
Transfering	* Endpoint	
Transfer log		
Point to point tran	* AccessKeyId	
Point to point log	* AccessKeySecret	
🔗 Share Manager 🛛 🗠	* BucketName	
Invitation upload		
Share download	Oss Home	
Email	* Slice Size	100 1MB ~ 5120MB
🛋 Users Manager 🛛 🔺		Test Save
Users		Tox Jurs.
Operation records		
User group		
Third-party auth		

# 2.9.3 Amazon S3

S3 ストレージの設定を入力し、[テスト]をクリックします。 通過したら、保存してください。次回起動すると有効になります。

😂 Raysync Enterpr	r <b>ise</b>   Admin Console					
E	Storage config					
E Server						
t≣ Transfer ^	* Storage Provider	🔿 Local storage 🔿 Alibaba cloud OSS	Amazon S3	<ul> <li>S3 interface compatible str</li> </ul>	orage 🔿 Azure Blob	
Transfering	* Region					
Transfer log	Region					
Point to point tran	* AccessKeyId					
Point to point log	* AccessKeySecret					
🔗 Share Manager 🛛 🗠	* BucketName					
Invitation upload						
Share download	S3 Home					
Email	* Slice Size	100		5MB ~ 5120MB		
🚉 Users Manager \land	L	Test	Save			
Users						
Operation records						
User group						



# 2.9.4 S3 インターフェース対応ストレージ

S3 インターフェース情報を入力し、[テスト]をクリックします。 通過したら、保存してください。次回起動すると有効になります。

😁 Raysync Enterpris	Se Admin Console	
Ē	Storage config	
Berver		
t≣ Transfer ^	* Storage Provider	🔿 Local storage 🔿 Alibaba cloud OSS 🔿 Amazon S3 💿 S3 interface compatible storage 🔿 Azure Blob
Transfering	* Endpoint	
Transfer log	Endpoint	
Point to point tran	Region	
Point to point log	* AccessKeyld	
🔗 Share Manager \land	* AccessKeySecret	
Invitation upload	needsheyseeree	
Share download	* BucketName	
Email	Storage Path	
🚉 Users Manager \land	* Slice Size	100 5MB ~ 5120MB
Users		
Operation records		Test
User group		

### 2.9.5 Azure Blob

azure blob インターフェース情報を入力し、[テスト]をクリックします。 通過したら、保存してください。次回起動すると有効になります。

SRaysync Enterprise   Admin Console						
Ē	Storage config					
📑 Server						
t≣ Transfer ^	* Storage Provider	Local storage Alibaba cloud OSS	O Amazon S3 O S3 interface con	npatible storage 💿 Azure Blob		
Transfering	* Connection string					
Transfer log	connection string					
Point to point tran	* container					
Point to point log	Blob path					
Share Manager ^	* Slice Size	100	1MB ~ 5120MB			
Invitation upload			1110 5120110			
Share download		Test	Save			
Email						
🚉 Users Manager 🛛 🗠	-					

% Tel: +86 18681593969



### 2.10 詳細設定

#### 2.10.1.1 TLS 証明書

Raysync は、ウェブ上の http 暗号化とファイル転送の暗号化の両方に使用可能な暗号化証明書 サービスを提供しています。デフォルトでは Raysync に付属の暗号化証明書を使用しています。 また、ユーザー自身の証明書を使って暗号化することもできます。

SRaysync Enterprise   Admin Conso	le
三 TLS certificate	
E Server	
t≣ Transfer ^ Upload	* SSL Pem
Transfering	Please copy and paste PEM code here
Transfer log	
Point to point tran	
Point to point log	
🔗 Share Manager 🛛 🗠	
Invitation upload	* SSL Key Please copy the key code and paste here
Share download	
Email	
🛋 Users Manager \land	
Users	
Operation records	
User group	Start to Opioad
Third-party auth	
Auth A/C setting Security	Prohibit non-SSL connections
Space statistics	Sava
Send notification	
Storage config	

### 2.10.1.2 TLS 証明書

非 SSL 接続の禁止を有効にすると、https://certificate ドメイン名:8091 を使用して、フロン トユーザーページにアクセスすることはできません。

証明書ファイルと証明書キーを入力して、[OK]をクリックすると、サーバーの再起動後に設定が 有効になります。



	milu-party autri	1.00		
	Auth A/C setting	Security	Prohibit non-SSL connections	
	Space statistics		Save	
	Send notification			
8	Storage config			
0	Advanced Setting ^			
	TLS certificate			
	Client TLS			
	MySQL config			

# 2.10.1.3 TLS 証明書情報の表示

TLS 証明書をアップロードした後、アップロードされた証明書の有効期間とドメイン名の情報を 確認できます。

SRaysync Enterprise   Admin Console						
Ē	TLS certificate					
E Server						
f≣ Transfer ^	Certificate	2018-12-20 2020-12-19				
Transfering	Densis					
Transfer log	Domain Name					
Point to point tran		Upload again				
Point to point log						
🔗 Share Manager 🛛 🔨	Security	Prohibit non-SSL connections				
Invitation upload		Save				
Share download						
Email						
🛋 Users Manager \land						

# 2.10.1.4 TLS 証明書の再アップロード

[再度アップロード]をクリックします。



🗲 Raysync Enterpr	iSe Admin Console
Ē	TLS certificate
Server	
l≣ Transfer ^	Certificate
Transfering	Validity 2018-12-20 2020-12-19
Transfer log	Domain Name *.raysync.cn
Point to point tran	Upload again
Point to point log	
🔗 Share Manager 🛛 ^	Security Prohibit non-SSL connections
Invitation upload	Save
Share download	
Email	
🛋 Users Manager 🛛 ^	
Users	

新しい SSLPem とキーをもう一度入力し、[アップロード]をクリックします。サーバーを再起動 すると有効になります。

2020-12-19	the certificate	×	
Please copy	y and paste PEM code here		
-SSL connections			
* SSL Key	a the bar and on donate long		
riease (0)			
	۵		
		Cancel Upload	
	2020-12-19  * SSL Pem Please cop SSL connections  * SSL key Please cop	2020-12-19   Re-upload the certificate   SSL connections	2020-12-19     * SSL Pem       SSL connections     * SSL Key       Please copy the key code and paste here

### 2.10.2 クライアント TLS

Rasync クライアント証明書は、2 つの方法を通じて取得できます。 1 つは、Alibaba クラウド oss から最新の証明書を取得することです。 デフォルトでは、Alibaba クラウドストレージ OSS から最新の証明書を取得することを選択して います oss 証明書が更新されると、Raysync は自動的に最新のクライアント証明書を OSS ストレ ージからダウンロードします。

Website: www.raysync.io & Tel: +86 18681593969 Email:support@raysync.io



😂 Raysync Enter	prise   Control Center
E	Client TLS
⊟ Server	
f≣ Transfer ^	Download from 🕜 Raysync server 💽 Alibaba OSS
Current transfers	*Tip: When your network is not accessible to the external network, please configure the certificate location as a Raysync server.
Transfer log	
🔗 Share Manager 🛛 🔿	Save
Invitation upload	
Share download	
Email	
🚉 Users Manager \land	
Users	
Operation records	
User group	
Third-party authe	
Space statistics	
Storage Configura	
Advanced Setting ^	
TLS certificate	
Client TLS	

2つ目は、Raysync サーバーからダウンロードすることです。

外部ネットワークにアクセスできない場合は、証明書の場所を Raysync サーバーに設定してください。

最新の証明書パッケージをアップロードする場合は、クリックしてください。証明書をアップロードしたら、「保存」をクリックします。ウェブ上で再度クライアントにログインすることで、 クライアント証明書をダウンロードすることができます。

😂 Raysync Enter	SRaysync Enterprise   Control Center				
E	Client TLS				
Server					
t≣ Transfer ^	Download from   Raysync server Alibaba OSS				
Current transfers	*Tip: When your network is not accessible to the external network, please configure the certificate location as a Raysync server.				
Transfer log					
🔗 Share Manager \land	Upload certificate Upload				
Invitation upload	Save				
Share download					
Email					
≡ Users Manager ∧					
Users					
Operation records					
User group					
Third-party authe					
Space statistics					
Storage Configura					
Advanced Setting      ^					
TLS certificate					
Client TLS					

🌭 Tel: +86 18681593969



### 2.10.3 MySQL 設定

Raysync は外部の MySQL データベースに対応しています。管理者がより柔軟なデータベース設定 方法を提供します。

アドレス、ポート、データアカウントとパスワードなど、外部データベースの設定を入力します。 テスト接続に成功すれば、[テスト]をクリックします。[0K]をクリックして外部データベースを 有効化し、バックグラウンドの設定情報がデータベースに保存されます。

SRaysync Enterprise   Control Center					
⋸	MvSQL configuration				
🗐 Server					
l≣ Transfer ^	□Enable external MySQL databa	ise			
Current transfers	Database address (ip or URL):				
Transfer log					
🔗 Share Manager \land	Database port:	3306			
Invitation upload	Database name:	raysync_db			
Share download	Database account:	raysync			
Email	11 601				
🚉 Users Manager 🛛 🗠	WySQL password:				
Users	Test connection	Submit			
Operation records	*Tips: Click the test button after	confirming that the information is correct.			
User group					
Third-party authe					

# 2.10.4 転送プロトコル

Raysync は4種類の転送プロトコル設定を提供します。

Ę	🛢 Raysync El	nter	<b>prise</b>   Control Center		
			Transmission protocol		
E	Server				
1	Transfer		Select Transport Protocol	Automatically select UDP/TCP When latency is less than 10 ms , switch to TCP	
	Current transfers	5		Only UDP	
	Transfer log			Only TCP	
ť	Share Manager	^		Default	
	Invitation upload	l.		Save	
	Share download				
	Email				
B	Users Manager	^			

- 1. UDP/TCP を自動的に選択:送信遅延が 10ms 未満の場合、TCP 送信に自動的に切り替えるよう に設定します。
- 🛞 Website: www.raysync.io 🛛 🗞 Tel: +86 18681593969 🛛 🖂 Email:support@raysync.io



SRaysync Enterprise   Control Center			
⊑ ≣ Server	Transmission protocol		
t≣ Transfer ^ Current transfers Transfer log	Select Transport Protocol  Automatically select UDP/TCP When latency is less than 10 ms , switch to TCP Only UDP Only TCP Default		
Invitation upload Share download Email	Save		
🚉 Users Manager \land			

2. UDP のみ:送信タスクには UDP モードのみを使用します

1	Raysync E	Enter	<b>orise</b>   Control Center			
Ū.			Transmission protocol			
B	Server					
1≣	Transfer	^	Select Transport Protocol	O Automatically select UDP/TCP	When latency is less than 10	ms , switch to TCP
	Current transfe	rs		Only UDP		
	Transfer log			Only TCP		
Ð	Share Manager	~		<ul> <li>Default</li> </ul>		
Ť		d		Save		
	Share downloa	d				
1	Email					
=1.	Users Manager	^				

3. TCP のみ:送信タスクには TCP モードのみを使用します

S Raysync Enterprise   Control Center			
드 目 Server	Transmission protocol		
f≣ Transfer ^ Current transfers Transfer log	Select Transport Protocol Automatically select UDP/TCP When latency is less than 10 ms , switch to TCP Only UDP Only TCP		
Share Manager ^ Invitation upload	Save		
Share download Email ■ Users Manager ^			

4. デフォルト:デフォルトでは UDP 転送が優先され、UDP 転送が中断されると自動的に TCP 転送に切り替わります。



ų	Raysync Er	nter	<b>prise</b>   Control Center			
	Conver		Transmission protocol			
6						
18	Transfer		Select Transport Protocol	Automatically select UDP/TCP	When latency is less than 10	ms , switch to TCP
	Current transfers			Only UDP		
	Transforlog			Only TCP		
	mansier log			Oefault		
6 <sup>1</sup>	Share Manager					
	Invitation upload			Save		
	Share download					
×.	Email					
=1	Users Manager					

# 2.10.5 イベント通知

イベント通知を設定すると、設定したプログラムはイベント終了時に実行されます。

😂 Raysync Enter	prise   Control Center admin
E	Event notification
E Server	
t≣ Transfer ^	Add www.t
Current transfers	
Transfer log	No Data
🔗 Share Manager 🛛 🗠	
Invitation upload	
Share download	
Email	
🚌 Users Manager \land	
Users	
Operation records	
User group	
Third-party authe	
Space statistics	
😞 Storage Configura	
Advanced Setting ^	
TLS certificate	
Client TLS	
MySQL configurat	
Transmission prot	
Event notification	

イベントの追加:[イベントの追加]をクリックします。

イベント情報を記入してください。



😂 Raysync Enter		
	Event notification	
	Add event Delete	Add event
		Event
		information
		Event type Uploaded 🗸
		*Event name
		Activate Event Remark
		Event operation
		Event Executable program V
		*Executable
		program path Command line
		parameters
		wait time
Advanced Setting      ^		OK Cancel
		Caliter

イベントの追加が成功した場合、操作の中の[テスト]をクリックすると、イベントが正しく設定 されていることをテストできます。

S Raysync Enterprise   Control Center admit										
Ξ Β Server	Event notification									
t≣ Transfer ^	Add event Delete									
Current transfers		Event name	Event type	Event operation	Status	Actions	Remark			
Transfer log		test	Uploaded	Executable program	Activated	Edit   Delete   Test				
Invitation upload							Page1-1/Total1 < 🚺 >	10/page v		
Share download										
Email										
🟨 Users Manager \land										

SRaysync Enterprise   Control Center									admin	
E	Event notification									
E Server										
t≣ Transfer ^	Add event Delete									
Current transfers		Event name	Event type	Event operation		Status		Actions	Remari	ĸ
Transfer log		test	Uploaded	Executable program		Activated		Edit   Delete   Test		
P Share Manager A										
Invitation upload									Page1-1/Total1	10/page v
Share download										
Email										
💵 Users Manager \land										

イベントを編集するには、操作で[編集]をクリックします

イベントを削除するには、操作の[削除]をクリックします

SRaysync Enterprise   Control Center admin								
≡ ⊜ Server	Event notification							
1≣ Transfer ^	Add event	Delete						
Current transfers	Ev	vent name	Event type	Event operation	Status	Actions	Remark	
P Share Manager	te	est	Uploaded	Executable program	Activated	Edit Delete   Test		
Invitation upload							Page1-1/Total1 ( 1 ) 10/page v	
Share download								
Email								
🚛 Users Manager \land								

🛞 Website: www.raysync.io 🛛 🗞 Tel: +86 18681593969 🛛 🖂 Email:support@raysync.io


## 2.10.6 その他の設定

## 2.10.6.1 速度制限

Other settings	
Speed Limit	User Maximum upload speed (Mbps): [0: unlimited]: 0 User Maximum download speed (Mbps): [0: unlimited]: 0

## 2.10.6.2 ログファイルの保存場所

ログファイルの保存場所として、設定したいパスを入力します。例えば、負荷分散を行う場合は、 ログアドレスを共有パスとして設定することができます。マスターサーバーとバックアップサー バーは、同じアドレスでログファイルを読み込むことができます。サーバーの再起動後に設定が 有効になります。

Log me	Storage location (Note: This modification need	is to restart the server to take effect.
	Save cycle (Note:This modification needs to re	estart the server to take effect.)
	Transfer log 30 day(s)	
	Operation log 30 day(s)	

## 2.10.6.3 ログファイル保存期間

転送ログとユーザー操作ログの期間を設定することができ、デフォルトは 30 日です。 設定後、[保存] ボタンをクリックします。サーバー情報ページの[再起動]をクリックすると、 有効になります。



😂 Raysync Enter	<b>prise</b>   Control C	enter
Ē	More settings	
E Server		
1≣ Transfer ^	Speed limit	User max upload speed (Mbps): [0: unlimited]
Current transfers		Ō
Transfer log		User max download speed (Mbps): [0: unlimited]
🔗 Share Manager 🛛 🗠		0
Invitation upload	Log	Log storage path: (Note: Please restart the server to refresh this modification)
Share download		Save cycle: (Note: Please restart the server to refresh this modification)
Email		Transfer log 30 day(s)
🚉 Users Manager \land		Operation log 30 day(s)

## 2.10.6.4 ファイルを閉じる

この機能を有効化すると、ファイルのアップロードが完了後に、バックエンドでファイルを閉じる操作が実行されます。

[非同期クローズを有効にする]ボタンにチェックを入れ、サーバーを再起動すると有効になります。

😂 Raysync Enterp	<b>orise</b>   Control C	Senter
Ē	More settings	
E Server		
1≣ Transfer ^	Speed limit	User max upload speed (Mbps): [0: unlimited]
Current transfers		0
Transfer log		User max download speed (Mbps): [0: unlimited]
🔗 Share Manager 🛛 🗠	Log	
Invitation upload	LOG	Log storage path. (note, riease restarcure server to remean this mounication)
Share download		Save cycle: (Note: Please restart the server to refresh this modification)
Email		Transfer log 30 day(s)
🛋 Users Manager \land		Operation log 30 day(s)
Users	Close File	Enable asynchronous close (Note: Please restart the server to refresh this modification)
	Sync	☑ Enable

## 2.10.6.5 ファイルの同期

この機能を有効化すると、ログイン後に同期タスクディレクトリを新規作成する機能が表示され ます。



SRaysync Enterprise   Control Center		
⊑ ⊟ Server	More settings	
t≣ Transfer ∧	Speed limit	User max upload speed (Mbps): [0: unlimited]
Current transfers Transfer log		User max download speed (Mbps): [0: unlimited]
Share Manager ^ Invitation upload	Log	0 Log storage path: (Note: Please restart the server to refresh this modification)
Share download		Save cycle: (Note: Please restart the server to refresh this modification)
Email 🛋 Users Manager 🛛 ^		Operation log 30 day(s)
Users	Close File Sync	Enable asynchronous close (Note: Please restart the server to refresh this modification)     Enable
Operation records User group	Modify Password Server IP	Enable     Support multiple IP addresses (Note: Please restart the server to refresh this modification)

😂 Raysync Enterp	rise		
A Personal Space	Personal Sp Create Sync Folder Task		
🕾 Group Space			
🔗 Share Management	All		
	Name 1	Size $\downarrow$	Modified $\downarrow$
	🗌 🗮 linux-3.4.113	μ.	-

## この機能を無効にした後、ユーザーは新規同期タスクディレクトリ機能を非表示にします。

Image: Server   Image: Server	😂 Raysync En	t <b>erprise</b>   Control Ce	nter
Server   I Transfer Speed limit User max upload speed (Mbps): [0: unlimited]   Current transfers User max download speed (Mbps): [0: unlimited]   Transfer log 0   Share Manager Log   Log Log storage path: (Note Please restart the server to refresh this modification)   Invitation upload   Share download   Email   Users   Users   Operation records   User group   Personal Space   Invitation upload   Since Manager   Invitation upload   Save cycle: (Note: Please restart the server to refresh this modification)    Invitation upload   Share download   Email   Users   Users   Users   Sync   Enable   Operation records   Modify Password   Enable   Server IP   Support multiple IP addresses   Invitation space   Invitation space   Since Manager   Since Manager   Since Manager   Since Manager   Invitation records   Invitation records   Since Manager   Invitation records   Since Manager   Since Manager   Invitation records   Since Manager   Invitat	11	More settings	
Image: Speed limit User max upload speed (Mbps): [0: unlimited]   Current transfers   Transfer log   Invitation upload   Share download   Enail   Image: Invitation upload   Share download   Enail   Users   Users   Operation records   Modify Password   Imable   Sync   Enable   User group	⊟ Server		
Current transfers       0         Transfer log       0         Invitation upload       0         Share download       Eag storage path: (Note: Please restart the server to refresh this modification)         Invitation upload       Save cycle: (Note: Please restart the server to refresh this modification)         Transfer log 30       day(s)         Operation log 30       day(s)         Users       Sync         Operation records       Modify Password         User group       Close File         Personal Space       Personal Space         Personal Space       Personal Space         A Brance       Modified 4         Mater       Modified 4	1≣ Transfer	<ul> <li>Speed limit</li> </ul>	User max upload speed (Mbps): [0: unlimited]
Transfer log User max download speed (Mbps): [0: unlimited]   Invitation upload Invitation upload   Share download Save cycle: (Note: Please restart the server to refresh this modification)   Email Transfer log 30 day(s)   Qperation log 30 day(s) Close File   Close File Enable   Sync Enable   Sync Enable   Server IP Support multiple IP addresses (Note: Please restart the server to refresh this modification)   Stare group Image: Personal Space   Group Space Image: Personal Space   Share Management Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space   Image: Personal Space Image: Personal Space	Current transfers		0
Invitation upload   Share download   Email   Bare download   Email   Operation log 30   day(s)   Close File   Invitation upload   Operation log 30   day(s)   Close File   Enable   Sync   Enable   Sync   Invitation upload   Modify Password   Enable   Server IP   Support multiple IP addresses   Whore Space   Image: Personal Space <	Transfer log		User max download speed (Mbps): [0: unlimited]
Log       Log storage path: (Note: Please restart the server to refresh this modification)         Invitation upload       Save cycle: (Note: Please restart the server to refresh this modification)         Email       Transfer log 30 day(s)         Email       Operation log 30 day(s)         Users       Sync         Sync       Enable         Operation records       Modify Password € Enable         User group       Support multiple IP addresses (Note: Please restart the server to refresh this modification)         *       Personal Space	Share Manager	~	0
Share download   Email   Transfer log 30   day(s)   Operation log 30   Users   Operation records   Modify Password © Enable   Operation records   Modify Password © Enable   Server IP   Support multiple IP addresses (Note: Please restart the server to refresh this modification) <b>Personal Space</b> <ul> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <li> <ul> <li> <ul> <li> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> <li> <ul> &lt;</ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></ul></li></li></ul></li></ul></li></li></ul></li></ul></li></ul></li></ul></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></li></ul></li></ul>	Invitation unload	Log	Log storage path: (Note: Please restart the server to refresh this modification)
Share download     Email     Transfer log 30 day(s)   Operation log 30 day(s)   Users   Operation records   Modify Password P Enable   Operation records   Modify Password P Enable   Server IP   Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses     Server IP     Server IP </th <th>Chara download</th> <th></th> <th></th>	Chara download		
Email     Imail     Operation log 30     Operation log 30     Operation records     Modify Password     Sync     Imail     Operation records     Modify Password     Sync     Support multiple IP addresses     Server IP     Server IP </th <th>Share download</th> <th></th> <th>Save cycle: (Note: Please restart the server to refresh this modification) Transfer log 30 day(s)</th>	Share download		Save cycle: (Note: Please restart the server to refresh this modification) Transfer log 30 day(s)
I Users Manager   Users   Operation records   User group     Sync   Enable   Server IP   Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP   Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Server IP     Support multiple IP addresses     Name 1     Name 1     Name 1     Size 4	Email		
Users       Sync       Enable         Operation records       Modify Password       Enable         User group       Support multiple IP addresses       (Note: Please restart the server to refresh this modification)         CRAysync Enterprise       Personal Space       Personal Space       Personal Space         Image: Share Management       All       Size ↓       Modified ↓	■ Users Manager	Close File	Fnable asynchronous close (Note: Please restart the server to refresh this modification)
Operation records Modify Password Enable   User group Server IP Support multiple IP addresses (Note: Please restart the server to refresh this modification)     Charles Personal Space   Image: Share Management Size 4     Name †   Size 4     Modified 4	Users	Sync	Enable
User group     Server IP   Support multiple IP addresses (Note: Please restart the server to refresh this modification)   Personal Space     A Personal Space     Image: Share Management     All     Name ↑     Size ↓        Modified ↓	Operation records	Modify Password	☑ Enable
A Personal Space   B Group Space   Image: Share Management   All   Image: Name ↑   Size ↓   Modified ↓	User group	Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
A Personal Space	🗲 Ravsvnc Enterp	ise	
A Personal Space       Personal Space			
A Group Space     (1)     (2)	A Personal Space	Personal Space	
	B Group Space		
□ rane - 5120 ↔ Modilied ↔	Share Management	All Name 6	Grad Medified (
		□ <mark>□</mark> linux-3.4.113	ore → Modimed ψ



## 2.10.6.6 アカウントのロック

ユーザーパスワードは、X 分以内に X 回間違えると、アカウントをロックするように設定するこ とができます。設定後に保存して、有効にします。

	Operation records	Modify Password	Enable			
	User group	Server IP	Support multiple IP addresses (Note: Please restart the s	erver to refresh this	modification)	
	Third-party authe	Process Num	Enable (Note: Please restart the server to refresh this modifie	tation)		
	Space statistics	Security	Lock account:			
ŝ	storage Configura		Account will be locked if the user enter password incorrec	tly for 5	times in 3	munites
۲	Advanced Setting ^	-	Weak password:			
	TLS certificate		Please enter the letters that are not allowed to be set, and use semicolon 'r' for different letter to separate. Such as			
	Client TLS		Kaysync123;Kaysync.	1		
	MySQL configurat		File format whitelist:			
	Transmission prot		Enable (Less than 255 characters)			
	Event notification		Please enter the suffix name that allows the user to transfer the file. Please use multiple formats; such as: txt; exe;			
	More settings			11		
ប	Personalization		Save			

## 2.10.6.7 弱いパスワード設定

ユーザーが設定できないパスワードを事前設定できます Raysync; raysync のように、複数のパ スワードを「;」で区切って使用します。設定後に保存して、有効にします。

Operation records	Modify Password	Z Enable
User group	Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
Third-party authe	Process Num	Enable (Note: Please restart the server to refresh this modification)
Space statistics	Security	1 Lock account:
😂 Storage Configura		Account will be locked if the user enter password incorrectly for 5 times in 3 munites
Advanced Setting      ^	F	Weak password:
TLS certificate		Please enter the letters that are not allowed to be set, and use semicolon '' for different letter to separate. Such as
Client TLS		naysync i cynaysync. Ir
MySQL configurat		File format whitelist:
Transmission prot		Enable (Less than 255 characters)
Event notification		Please enter the suffix name that allows the user to transfer the file. Please use multiple formats; such as: txt; exe;
More settings		
ල Personalization		Save

## 2.10.6.8 システム転送ホワイトリスト

システムがアップロードを許可する、ファイル形式の設定に使用します。 [転送ホワイトリストのファイル形式を開く]にチェックを入れ、下の入力欄にユーザーがアップ ロード可能なファイル形式を入力します。「txt; iso; mp4」のように、複数のフォーマットを 「;」で区切ってから、[OK]をクリックして保存します。

Website: www.raysync.io % Tel: +86 18681593969 Mail:support@raysync.io



Operation records Modify Passwo	ord 🗹 Enable
User group Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
Process Num Third-party authe	<b>Enable</b> (Note: Please restart the server to refresh this modification)
Space statistics	1
Security	Lock account:
Storage Configura	Account will be locked if the user enter password incorrectly for 5 times in 3 munites
Advanced Setting      ^	Weak password:
TLS certificate	Please enter the letters that are not allowed to be set, and use semicolon <sup>15</sup> for different letter to senarate. Such as
Client TLS	Raysync123:Raysync.
MySQL configurat	File format whitelist:
Transmission prot	Enable (Less than 255 characters)
Event notification	Please enter the suffix name that allows the user to transfer the file. Please use multiple formats; such as: txt; exe;
More settings	
	Save

## 2.10.6.9 複数の IP アドレスに対応

Close File	Enable asynchronous close (Note: Please restart the server to refresh this modification)
Sync	Enable
Modify Password	Enable
Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
Process Num	Enable (Note: Please restart the server to refresh this modification)
	1

## 2.10.6.10 許可されたプロセス数

Close File	Enable asynchronous close (Note: Please restart the server to refresh this modification)
Sync	Enable
Modify Password	Enable
Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
Process Num	Enable (Note: Please restart the server to refresh this modification)
	1



## 2.10.6.11 ユーザーによるパスワードの変更を許可する

Close File	Enable asynchronous close (Note: Please restart the server to refresh this modification)
Sync	✓ Enable
Modify Password	Z Enable
Server IP	Support multiple IP addresses (Note: Please restart the server to refresh this modification)
Process Num	Enable (Note: Please restart the server to refresh this modification)

# 2.11 管理者情報を変更する

管理者アカウントとパスワードの変更に対応しています。 [管理者編集]をクリックします

😂 Raysync Enterp	<b>prise</b>   Control Center			admin
E Server	Server			Edit Administrator
t≣ Transfer ^	User connections	Storage Status	License Information:	() Log Out
Current transfers	Online Users Client connections		Activated (10000Mbps)	Details
Transfer log	1 1			
Invitation upload	After login, each web page will be counted as an online user, and after start the client, each page will be counted as a client connection	Used0.67%	Server Status	
Share download		91,46 TB free of 92.09 TB		
Email	Main Information Modify	CPU info		
Users	Server Name : RaySync Server	70	CPU Usage (%)	
Operation records	Version : 5.0.3.9	60		
User group	Device ID :	50		
Third-party authe	System :	40		
Space statistics	UDP Accelerate 32001	20		
Advanced Setting ^	Port UDP Package 1200 Cire -	10		

😂 Raysync Enter	<b>prise</b>   Control Center	
E	Edit Administrator	
Server		
f≣ Transfer ^	Account	admin
Current transfers		Account format can only be (letters, numbers, underscores)
Transfer log	Old Password	Old Password
Share Manager ^	New Password	New Password
Invitation upload	New Password Again	Password must be 8-20 characters and include lowercase letters, uppercase letters, numbers, and special characters. Not be identical to the account name.           New Password Again
Share download		
Email	OK	Back
🚉 Users Manager \land		

[パスワードが変更されました]と表示されから、ログインページに切り替えます。



🗲 Rays	ync Enterp	rise
Admin Manag	ement Login	
Account		
Password		
	Log In	

# 2.12 個性的設定

# 2.12.1 アイコン、ロゴ、背景画像など

SRaysync Enterprise   Control Center				
Ē	Personalization			
E Server				
t≣ Transfer ^	Custom ico Upload (Use '.ico' suffix format image)			
Current transfers	Custom logo Upload (recommended 165 x 55 size image)			
Transfer log	Login the home page Upload (recommended for 1920 x 1080 size images)			
🔗 Share Manager 🛛 🗠	background image			
Invitation upload	Jave Reset			
Share download				
Email	Set web pages' Company Name			
🛋 Users Manager \land	keywords			
Users	English Shenzhen Yunyu Technology Co., Ltd			
Operation records	Product name			

(1) アイコン画像をアップロードします。



😂 Raysync Enterpri	Se Admin Console					
⊑ ⊟ Server	Personalization					
t≣ Transfer ^	Custom Ico	Upload	(Support ima	age with suffix '.ico		
Transfering	Custom Logo	Upload	(Recomment	d image with size 1	65 x 55)	
Transfer log	Login Background	Upload	(Recommend	d image with size 1	920 x 1080)	
Point to point tran		Sav	e	Reset		
Point to point log						
Share Manager ^						
実際の効果 :						

-	9	Raysy	/nc Ma	nager	×	+
	←	$\rightarrow$	G		demo.raysync.cn:	9091/admin/login

(2) ロゴ画像のアップロードします

ヒント:また、アップロードされたカスタムロゴに従って、メールやユーザーページのロゴも変 更されます。

😂 Raysync Enterpri	Se Admin Console				
Ξ	Personalization				
E Server					
1≣ Transfer ^	Custom Ico	Upload	(Support imag	ge with suffix '.ico')	
Transfering	Custom Logo	Upload	(Recommend	image with size 165 :	c 55)
Transfer log	Login Background	Upload	(Recommend	image with size 1920	x 1080)
Point to point tran		Save	e	Reset	
Point to point log				1014204	
🔗 Share Manager \land					

(3) 背景画像をアップロードします。

ヒント:アップロードされたカスタム背景に従って、ログインページも変更されます。



😂 Raysync Enterpr	<i>İSE</i> Admin Console		
Ξ	Personalization		
Server			
t≣ Transfer ^	Custom Ico	Upload	(Support image with suffix '.ico')
Transfering	Custom Logo	Upload	(Recommend image with size 165 x 55)
Transfer log	Login Background	Upload	(Recommend image with size 1920 x 1080)
Point to point tran		Save	e Reset
Point to point log			
🔗 Share Manager 🛛 🔺			

[リセット]をクリックすると、個性的設定がクリアされ、デフォルトの設定に戻ります。

😂 Raysync Enterpr	ISE Admin Console		
드 目 Server	Personalization		
1≣ Transfer ^	Custom Ico	Upload	(Support image with suffix '.ico')
Transfering	Custom Logo	Upload	(Recommend image with size 165 x 55)
Transfer log	Login Background	Upload	(Recommend image with size 1920 x 1080)
Point to point tran		Save	re Reset
Point to point log			
Share Manager ^			

# 2.12.2 ウェブページのキーワードをカスタマイズ

Share download		
Email	Product Info	Company name
🞫 Users Manager 🛛 🔺		English Shenzhen Yunyu Technology Co., Ltd
Licore		Product name
03613		English <sub>Raysync</sub>
Operation records		Company website
User group		English http://www.raysync.io
Third_narty authe		Configure URL
minu-party addie		raysync://
Space statistics		Save Reset
Storage Configura		
Advanced Setting ~		
Personalization		

Email:support@raysync.io

会社名、商品名、会社のホームページ、URL をカスタマイズできます。

Website: www.raysync.io % Tel: +86 18681593969



ヒント:

会社名:管理コンソールページとメール通知(ダウンロード共有、アップロード招待と他のメー ル)の下隅に表示されます。

商品名:ユーザーのログインページとメール通知(ダウンロード共有、アップロード招待と他の メール)に表示されます。

会社のウェブサイト:管理画面の下隅にある会社名をクリックするか、共有ページにアクセスす るとウェブサイトにジャンプします。

会社 URL:フロントエンドユーザページが Raysync ソフトウェアのクライアントを起動するため に使用されます(URL はクライアントをカスタマイズする場合にのみ変更します)。通常では、 URL を変更しないでください。変更すると、通常の使用に影響する可能性があります。クライア ントをカスタマイズしたい場合は、ご相談ください)。

[リセット]をクリックすると、個性的設定がクリアされ、デフォルトの設定に戻ります。

Invitation upload	Product Info	Company name
Share download		English Shenzhen Yunyu Technology Co., Ltd
Email		Product name
Effiali		English <sub>Raysync</sub>
🚉 Users Manager 🛛 🔺		Company website
Users		English http://www.raysync.io
Operation records		Configure URL
Operation records		raysync://
User group		Save
Third-party auth		
Auth A/C setting		

# 3. よくある質問

## 3.1 ウェブサイトが Raysync に接続できません。

1. Raysync が起動し、右下のアイコンが表示されていることを確認してください。ウェブページ の[開始]をクリックします。

2.360、Kingsoft AntiVirus ソフトなどの保護下で Raysync を起動しない場合、ユーザーレジス トリが通常通りに書き込めず、Webページから起動できない可能性があります。一方、RavSync は手動で操作する必要があります。

3. Raysync アイコンを右クリックしてエラー検出を選択し、ローカルドメイン名解析、システム 時刻、システムエージェントと証明書の状態が「正常」であることを確認してください。また、 Raysync が起動されているかどうか、「クライアントが起動されていません」の表示が出ている かどうかを確認してください。システムエージェントが異常を表示したときは、エージェントが オンになっている可能性があります。起動する前に Raysync クライアントをシャットダウンして ください。 証明書が異常の場合は、Raysync クライアントのバージョンが最新かどうか、証明 書の有効期限が切れていないことを確認してください。

### 3.2 ウェブページ プロンプトサーバー 接続タイムアウト

🛞 Website: www.raysync.io 🛛 🗞 Tel: +86 18681593969



### クライアントチェック:

Raysync アイコンを右クリックして[エラー検出]を選択し、[サーバードメイン名]と[サーバー アドレス]が正しいかどうかを確認してください。cmd コマンドライン ping することで、解析ア ドレスの接続を確認することができます。

### サーバーチェック:

サーバーはユーザーの許可、ホームディレクトリなどの情報変更、クライアントを再起動する必 要性を確認します。

### 3.3 クライアントログインタイムアウト

クライアントを右クリックして、Raysync 設定の UDP メッセージサイズをより小さい値に変更し てください。

### 3.4 アップロードとダウンロード速度に差がある。期待していた速度が違う。

### クライアントチェック:

外部ネットワークの帯域幅をテストしてください。速度テストでは、ローカルアップロードとダ ウンロードの帯域幅を検出し、制限速度に達しているかどうかを確認します。

クライアントの通信事業者とサーバーの通信事業者が一致しているか確認してください。

#### サーバーチェック:

1. 関連サーバーのバックグラウンドを入力して、ライセンスの有効化を確認してください。ライ センス情報に記載されている帯域幅は想定される帯域幅であることを確認してください。

2. 現サーバーのネットワークトラフィックを開き、他のユーザーがサーバーの帯域を占有していないかを確認してください。

3. サーバーディスク読み取り/書き込み値がピークに達しているかどうかを確認してください。 他のユーザーがファイルの読み取り/書き込みを行っている場合、読み取り/書き込みが影響され る可能性があります。

### 3.5 ダウンロードパス。ネットワークパスを選択したけど、ダウンロー

### ドしたファイルが見つからない

ネットワークディスクへのパスをマップし、古いタスクを削除してください。再度ダウンロード し、保存したネットワークディスクパスを選択します。

### 3.6 ファイルのアップロード、ダウンロードは良く[ファイルを読み込

### んでいます]と表示される

### クライアントチェック:

1.転送先のディレクトリに、ファイルが大量に入っていないことを確認してください。ファイル 数と関係なく、クライアントがファイルを読み込むのを待つ必要があります。 2.右クリックして RaySync のタイムアウト時間を 60 秒以上に設定し、古いタスクを削除して送 信タスクを再度選択してください;

🛞 Website: www.raysync.io 🛛 💊 Tel: +86 18681593969 🛛 🖂 Email:support@raysync.io



### サーバーチェック:

サーバー下のディレクトリの読み込み性能を確認します。例:サーバーのディレクトリを入力して 1s を実行し、高速に応答します。du-a | wc-1 を実行して、ディレクトリ下のファイル数を カウントします。

🗞 Tel: +86 18681593969