

## Quick Start Guide of Server Deployment

### ● Linux Server

The RaySync windows server supports the deployment of windows server 2008/ windows server 2012/ windows server 2016/windows 7 / windows 8/windows 10 platforms.

#### 1 Get installation zip file

Visit <https://www.raysync.io/pricing/> and download the latest free or SMB zip file. If you purchased enterprise version, please contact the salesman.

#### 2 Unzip and start running

```
tar -zxvf RaySync-5.0.7.8-9476-free.tar.gz
cd RaySync
./install
./start
```

#### 3 Open port

If you deploy the server in the NAT gateway and there is only intranet IP, you need to open the following ports on the router NAT:

Server description	Protocal type	Port
User portal http service port	TCP	8090
User portal https service port		8091
Admin portal http service port	TCP	9090
Admin portal https service port		9091
Transmission non-encrypted service port	TCP	2442
Transmission TLS encryption service port		2443
UDP accelerated transmission service port	UDP	32001
Node management service port	TCP	32001
User portal webpage direct connection port	TCP	2480
User portal webpage encryption point to point connection port	TCP	2481

#### 4 Login admin console

Web address: [Server IP:9090/admin](#) (example: [192.17.45.56:9090/admin](#))



Admin account: [admin](#)

Admin password: please check file 'AdminInitPwd'(Automatically generated after starting the service in step 2)


```
root@iZwz9bx129zrqxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8# cat AdminInitPwd
3u( _w%!c
root@iZwz9bx129zrqxz2ief8dZ:/home/3.4.2.8/RaySync_3.4.2.8# █
```

#### 5 Server Activation

Enter your License to active. If your network cannot access the external network, please refer to "**Linux Offline Activation Authorization**".



## 6 Add User



## 7 User login

Web address: [Server IP:8090](#) (example: [192.17.45.56:8090](#))

Enter account and password, Follow the tip on the webpage to download the Raysync client,install and start to transfer.

## ● Windows Server

The RaySync windows server supports the deployment of windows server 2008/ windows server 2012/ windows server 2016/windows 7 / windows 8/windows 10 platforms.

### 1 Get installation zip file


Visit <https://www.raysync.io/pricing/> and download the latest free or SMB zip file. If you purchased enterprise version, please contact the salesman.

### 2 Unzip the installer

Unzip to any directory.

### 3 Start running

Doubleclick file 'start.bat' to launch the Raysync transmission.



### 4 Open port

If you deploy the server in the NAT gateway and there is only intranet IP, you need to map the following ports on the router NAT:

Server description	Protocal type	Port
User portal http service port	TCP	8090
User portal https service port		8091
Admin portal http service port	TCP	9090
Admin portal https service port		9091
Transmission non-encrypted service port	TCP	2442
Transmission TLS encryption service port		2443
UDP accelerated transmission service port	UDP	32001
Node management service port	TCP	32001
User portal webpage direct connection port	TCP	2480
User portal webpage encryption point to point connection port	TCP	2481

### 5 Login admin console

Web address: [Server IP:9090/admin](#) (example: [192.17.45.56:9090/admin](#))



Admin account: [admin](#)

Admin password: please check file 'AdminInitPwd' (Automatically generated after starting the service in step 3)


Name	Date modified	Type	Size
cfg	2/5/2021 6:50 PM	File folder	
config	3/2/2021 7:38 PM	File folder	
data	2/5/2021 6:50 PM	File folder	
dist	2/5/2021 6:50 PM	File folder	
doc	2/5/2021 6:50 PM	File folder	
dump	3/2/2021 3:44 PM	File folder	
httpscert	2/5/2021 6:50 PM	File folder	
log	3/2/2021 3:44 PM	File folder	
proxy	3/2/2021 3:44 PM	File folder	
tools	2/5/2021 6:50 PM	File folder	
AdminInitPwd	3/2/2021 3:44 PM	File	1 KB
AdminUnlockTool	2/5/2021 6:50 PM	Application	9,628 KB
api-ms-win-core-console-l1-1-0.dll	2/5/2021 6:50 PM	Application extens...	12 KB

## 6 Server Activation

Enter your License to active. If your network cannot access the external network, please refer to "**Windows Offline Activation Authorization**".



## 7 Add User



## 8 User login

Web address: [Server IP:8090](#) (example: [192.17.45.56:8090](#))

Enter account and password, Follow the tip on the webpage to download the Raysync client,install and start to transfer.